

Convert a reconstruction into a flux balance analysis model

Author(s): Ronan Fleming, Leiden University, Ines Thiele, National University of Ireland, Galway

Reviewers:

INTRODUCTION

Even with quality control during the reconstruction process, it is not appropriate to assume that any reconstruction can be converted directly into a model and used to make predictions. A model must satisfy certain assumptions before it can be used to make reliable predictions. Depending on the type of model, these assumptions will be different. Each assumption should be chemically or biologically motivated and expressed in an unambiguous manner and preferably both intuitively and mathematically. Flux balance analysis is a mathematical method widely used for studying genome-scale biochemical network. Here one aims to predict steady-state reaction fluxes, where there is a balance between production and consumption of each molecular species that is not exchanged across the specified boundary of a system. In this situation, one might obtain erroneous predictions if the system boundary is incorrectly specified. If a reconstruction contains one or more supposedly mass balanced reactions, but which are actually not mass balanced, such reactions in a model can lead to inadvertent leakage of a metabolite from the model, in violation of mass balance. Similarly, when generating a model for flux balance analysis, it is important to ensure that the network is flux consistent, that is, each reaction can carry a non-zero steady state flux.

Given a reconstruction with \hat{m} reactants involved in \hat{n} reactions, this tutorial demonstrates a method to identify and extract the largest subset of the reconstruction whose internal reactions are both stoichiometrically and flux consistent and whose external reactions are flux consistent. This model is then mathematically consistent with the basic requirements for generation of predictions using flux balance analysis. The identification of the component of the reconstruction that does not satisfy the aforementioned modelling conditions is also useful for targeting reconstruction effort towards resolving stoichiometric inconsistency or resolving flux inconsistency. The example used in this tutorial illustrates the process of extracting a model consistent with flux balance analysis, from a ReconX reconstruction.

PROCEDURE

Select reconstruction to convert into a model and enter parameters

Load the ReconX reconstruction, and save the original reconstruction in the workspace, unless it is already loaded into the workspace.

```
clear model
if ~exist('modelOrig','var')
    %select your own model, or use Recon2.0model instead
    if 0
        filename='Recon3.0model';
        directory='~/work/sbgCloud/programReconstruction/projects/
recon2models/data/reconXComparisonModels';
        model = loadIdentifiedModel(filename,directory);
```

```

else
    filename='Recon2.0model.mat';
    if exist('Recon2.0model.mat','file')==2
        model = readCbModel(filename);
    end
end
model.csense(1:size(model.S,1),1)='E';
modelOrig = model;
else
    model=modelOrig;
end

```

Set the level of printing, zero for silent, higher for more output.

```
printLevel=2;
```

Choose the directory to place the results

```

basePath='~/work/sbgCloud/';
resultsPath=[basePath '/programReconstruction/projects/recon2models/results/
reconXs/' model.modelID];
resultsFileName=[resultsPath filesep model.modelID];

```

Create and enter the folder for the results if it does not already exist

```

if ~exist(resultsPath,'dir')
    mkdir(resultsPath)
end
cd(resultsPath)

```

Optionally create a diary to save the output in case it is very long, this makes it easier to search, especially when debugging the process during the early stages.

```

if 0
    diary([resultsFileName '_diary.txt'])
end

```

Overview some of the key properties of the reconstruction

Noting the initial size of the reconstruction is useful for comparisons later with subsets derived according to mathematical specifications.

```

[nMet,nRxn]=size(model.S);
fprintf('%6s\t%6s\n','#mets','#rxns')

```

```
#mets      #rxns
```

```
fprintf('%6u\t%6u\t%s\n',nMet,nRxn,' totals.')
```

```
5063      7335      totals.
```

Make sure the stoichiometric matrix is stored in a sparse format as this accelerates computations with large networks

```
model.S=sparse(model.S);
```

Check in case the reconstruction is a model that is already ready for flux balance analysis

There is no need to run this live script any further if the reconstruction already satisfies the conditions necessary for flux balance analysis. That is if all internal reactants and reactions are stoichiometrically consistent, and all reactions are flux consistent, then the reconstruction satisfies the criteria to designate it a model ready for flux balance analysis.

SIntMetBool m x 1 Boolean of metabolites heuristically though to be involved in mass balanced reactions.

SIntRxnBool n x 1 Boolean of reactions heuristically though to be mass balanced.

SConsistentMetBool m x 1 Boolean vector indicating consistent mets

SConsistentRxnBool n x 1 Boolean vector indicating consistent rxns

fluxConsistentMetBool m x 1 Boolean vector indicating flux consistent mets

fluxConsistentRxnBool n x 1 Boolean vector indicating flux consistent rxns

```
if all(isfield(model,{ 'SIntMetBool','SIntRxnBool','SConsistentMetBool',...  
    'SConsistentRxnBool','fluxConsistentMetBool','fluxConsistentRxnBool'}))  
    if all(model.SIntMetBool & model.SConsistentMetBool)...  
        && nnz(model.SIntRxnBool &  
model.SConsistentRxnBool)==nnz(model.SIntRxnBool)...  
        && all(model.fluxConsistentMetBool)...  
        && all(model.fluxConsistentRxnBool)  
        fullyStoichAndFluxConsistent=1;  
        fprintf('%s\n','Reconstruction is a model that is already ready for  
flux balance analysis')  
    end  
    return  
else  
    fullyStoichAndFluxConsistent=0;  
    fprintf('%s\n','Reconstruction must be tested to check if it is ready  
for flux balance analysis')  
end
```

Reconstruction must be tested to check if it is ready for flux balance analysis

Manually remove certain reactions from the reconstruction

Before attempting to algorithmically remove stoichiometrically or flux inconsistent supposed internal reactions from a reconstruction to generate a model, there is an option to review the content of the reconstruction and manually identify reactions for removal. That is, there are two options:

A. Skip manual review of reconstruction content. Move to the next step.

B. Review the content of the reconstruction and omit any reactions that are assumed to be stoichiometrically or flux inconsistent. With respect to stoichiometric inconsistency, such reactions may be obviously mass imbalanced and not satisfy the heuristic conditions for identification as an external reaction. Alternatively, such reactions may be identified by a previous pass through of this tutorial as being of unknown stoichiometric consistency (`model.unknownSConsistencyRxnBool(j)==1`), after the largest stoichiometrically consistent subset of the network has been identified. This is an iterative process where multiple rounds of identification of the largest stoichiometrically consistent set and manual curation of the remainder that is of unknown stoichiometric consistency is necessary.

```
if strcmp(filename, 'Recon3.0model')
    modelOrig=model;
    if 0
        if 1
            %Rename some of the biomass reactions to make them more
            obviously exchange
            %reactions
            model.rxns{strcmp(model.rxns, 'biomass_reaction')}=
            'EX_biomass_reaction';
            model.rxns{strcmp(model.rxns, 'biomass_maintenance')}=
            'EX_biomass_maintenance';
            model.rxns{strcmp(model.rxns, 'biomass_maintenance_noTrTr')}=
            'EX_biomass_maintenance_noTrTr';

            %ATP hydrolysis is not imbalanced like all the other demand
            reactions so
            %give it a different accronym ATPM = ATP Maintenance
            bool=strcmp('DM_atp_c_', model.rxns);
            model.rxns{bool}='ATPM';
        end
        [model, removeMetBool, removeRxnBool] =
        manuallyAdaptRecon3(model, printLevel);
    else
        [model, removeMetBool, removeRxnBool] =
        manuallyAdaptRecon3Ines(model, printLevel);
    end
    [nMet0, nRxn0]=size(modelOrig.S);
    [nMet, nRxn]=size(model.S);
    if nMet0==nMet && nRxn0==nRxn && printLevel>0
        fprintf('%s\n', '--- Manually removing rows and columns of the
        stoichiometric matrix---')
        fprintf('%6s\t%6s\n', '#mets', '#rxns')
        fprintf('%6u\t%6u\t%6s\n', nMet0, nRxn0, ' totals.')
        fprintf('%6u\t%6u\t%6s\n', nMet0-nMet, nRxn0-nRxn, ' manually removed.')
```

```

        fprintf('%6u\t%6u\t%s\n',nMet,nRxn,' remaining.')
    end
end

```

Remove any trivial rows and columns of the stoichiometric matrix

Remove any zero rows or columns of the stoichiometric matrix

```

modelOrig=model;
model=removeTrivialStoichiometry(model);
[nMet0,nRxn0]=size(modelOrig.S);
[nMet,nRxn]=size(model.S);
if nMet0==nMet && nRxn0==nRxn && printLevel>0
    fprintf('%s\n','---Checking for Remove any trivial rows and columns of
the stoichiometric matrix----')
    fprintf('%6s\t%6s\n','#mets','#rxns')
    fprintf('%6u\t%6u\t%s\n',nMet0,nRxn0,' totals.')
    fprintf('%6u\t%6u\t%s\n',nMet0-nMet,nRxn0-nRxn,' duplicates removed.')
    fprintf('%6u\t%6u\t%s\n',nMet,nRxn,' remaining.')
end

```

```

---Checking for Remove any trivial rows and columns of the stoichiometric matrix----
#mets      #rxns
  5063      7335      totals.
     0         0      duplicates removed.
  5063      7335      remaining.

```

Check for duplicate columns by detecting the columns of the S matrix that are identical upto scalar multiplication.

```

modelOrig=model;
dupDetectMethod='FR';
dupDetectMethod='S';
removeFlag=0;
[modelOut,removedRxnInd, keptRxnInd] =
checkDuplicateRxn(model,dupDetectMethod,removeFlag,printLevel-2);

```

Remove any duplicate reactions, and uniquely involved reactants, from the stoichiometric matrix.

```

if length(removedRxnInd)>0
    irrevFlag=0;
    metFlag=1;
    %set all reactions reversible that are duplicates
    model.lb(removedRxnInd)=-model.ub(removedRxnInd);
    %remove duplicates
    model = removeRxns(model,model.rxns(removedRxnInd),irrevFlag,metFlag);
end

```

Display the statistics on the duplicate reactions,

```

[nMet0,nRxn0]=size(modelOrig.S);

```

```
[nMet,nRxn]=size(model.S);
if nMet0==nMet && nRxn0==nRxn && printLevel>0
    fprintf('%s\n','---Remove any duplicate reactions---')
    [nMet0,nRxn0]=size(modelOrig.S);
    [nMet,nRxn]=size(model.S);
    fprintf('%6s\t%6s\n','#mets','#rxns')
    fprintf('%6u\t%6u\t%s\n',nMet0,nRxn0,' totals.')
    fprintf('%6u\t%6u\t%s\n',nMet0-nMet,nRxn0-nRxn,' duplicates removed.')
    fprintf('%6u\t%6u\t%s\n',nMet,nRxn,' remaining.')
end
```

```
---Remove any duplicate reactions---
#mets      #rxns
  5063      7335      totals.
      0         0      duplicates removed.
  5063      7335      remaining.
```

Remove any duplicate reactions upto protons

Remove reactions reactions that differ only in the number of protons involved as substrates or products. Also remove exclusively involved reactants.

Save a temporary model for testing, before making any changes.

```
modelH=model;
```

Find the proton indicies in different compartments. A proton, with index i, is asumed to be represented by an abbreviation within model.mets{i} like h[*], where * denotes the compartment symbol.

```
nMetChars=zeros(length(modelH.mets),1);
for m=1:length(modelH.mets)
    nMetChars(m,1)=length(modelH.mets{m});
end
protonMetBool=strncmp(modelH.mets,'h',1) & nMetChars==length('h[*]');
if printLevel>2
    disp(modelH.mets(protonMetBool))
end
```

Zero out the proton stoichiometric coefficients from the temporary model for testing

```
modelH.S(protonMetBool,:)=0;
```

Check for duplicate columns, upto protons, by detecting the columns of the S matrix that are identical upto scalar multiplication.

```
dupDetectMethod='FR';
removeFlag=0;
[modelOut,removedRxnInd, keptRxnInd] =
checkDuplicateRxn(modelH,dupDetectMethod,removeFlag,printLevel-1);
```

Checking for reaction duplicates by stoichiometry (up to orientation) ...

```

Keep:      BTnt2      btn[e]      <=>      btn[c]
Duplicate:  BTnt4i     btn[e]      ->      btn[c]
Warning: EX_h(e) has more than one replicate
Keep:      EX_h(e)      <=>
Duplicate:  Htr        <=>
Keep:      GLCtlr      glc_D[e]      <=>      glc_D[c]
Duplicate:  GLCt2_2     glc_D[e]      <=>      glc_D[c]
Keep:      NACUP       nac[e]      ->      nac[c]
Duplicate:  NACDe       nac[c]      ->      nac[e]
Keep:      ORNt4m      orn[m] + citr_L[c]      <=>      orn[c] + citr_L[m]
Duplicate:  r0947      orn[m] + citr_L[c]      ->      orn[c] + citr_L[m]

```

Remove any duplicate reactions from the stoichiometric matrix, but do not remove the protons.

```

if length(removedRxnInd)>0
    irrevFlag=0;
    metFlag=0;%dont remove the protons
    model = removeRxns(model,model.rxns(removedRxnInd),irrevFlag,metFlag);
end

```

Display statistics of the removed reactions

```

if printLevel>0
    [nMet0,nRxn0]=size(modelOrig.S);
    [nMet,nRxn]=size(model.S);
    fprintf('%6s\t%6s\n','#mets','#rxns')
    fprintf('%6u\t%6u\t%6s\n',nMet0,nRxn0,' totals.')
    fprintf('%6u\t%6u\t%6s\n',nMet0-nMet,nRxn0-nRxn,' duplicate reactions
upto protons removed.')
    fprintf('%6u\t%6u\t%6s\n',nMet,nRxn,' remaining.')
end

```

| #mets | #rxns | |
|-------|-------|---|
| 5063 | 7335 | totals. |
| 0 | 5 | duplicate reactions upto protons removed. |
| 5063 | 7330 | remaining. |

```

%model size
[nMet,nRxn]=size(model.S);

```

Heuristically identify exchange reactions and metabolites exclusively involved in exchange reactions

An external reaction is one that is heuristically identified by a single stoichiometric coefficient in the corresponding column of *S*, or an (abbreviated) reaction name matching a pattern (e.g. prefix EX_) or an external subsystem assignment. Any remaining reaction is assumed to be an internal reaction. If a reaction is not external then it is denoted an internal reaction. External reactants are exclusively involved in exchange reactions, and internal reactants otherwise. The findSExRxnInd function finds the external reactions in the model which export or import mass from or to the model, e.g. Exchange reactions, Demand reactions, Sink reactions.

```

if ~isfield(model,'SIntMetBool') || ~isfield(model,'SIntRxnBool')

```

```

    model = findSExRxnInd(model,[],printLevel-1);
end

```

EXPECTED RESULTS

In the returned model, `model.SIntRxnBool`, is a boolean of reactions heuristically though to be mass balanced, while `model.SIntMetBool` is a boolean of metabolites heuristically though to be involved in mass balanced reactions.

CAUTION

The aforementioned assignments of external and internal reactions and reactants is the result of a heuristic and might result in one or more errors, either due to misspecification or because the names of external reactions and external subsystems often vary between laboratories.

Find the reactions that are flux inconsistent

Ultimately we seek to identify the set of stoichiometrically consistent reactions that are also flux consistent, with no bounds on reaction rates. However, finiding the stoichiometrically consistent subset can be demanding for large models so first we identify the subset of reactions that are flux consistent and focus on them.

```

modelOrig=model;
model.lb(~model.SIntRxnBool)=-1000;
model.ub(~model.SIntRxnBool)= 1000;
if 1
    if ~isfield(model,'fluxConsistentMetBool') ||
~isfield(model,'fluxConsistentRxnBool')
        param.epsilon=1e-4;
        param.modeFlag=0;
        param.method='null_fastcc';
        %param.method='fastcc';

[fluxConsistentMetBool,fluxConsistentRxnBool,fluxInConsistentMetBool,fluxInCo
nsistentRxnBool,model] = findFluxConsistentSubset(model,param,printLevel-1);
end
% Remove reactions that are flux inconsistent
if any(fluxInConsistentRxnBool)
    irrevFlag=0;
    metFlag=1;
    model =
removeRxns(model,model.rxns(fluxInConsistentRxnBool),irrevFlag,metFlag);
[nMet0,nRxn0]=size(modelOrig.S);
[nMet,nRxn]=size(model.S);

if printLevel>0
    fprintf('%s\n','-----')
    fprintf('%6s\t%6s\n','#mets','#rxns')
    fprintf('%6u\t%6u\t%s\n',nMet0,nRxn0,' totals.')
    fprintf('%6u\t%6u\t%s\n',nMet0-nMet,nRxn0-nRxn,' flux
inconsistent reactions removed.')

```



```

        fprintf('%6u\t%6u\t%s\n',nMet,nRxn,' remaining.')
        fprintf('%s\n','-----')
        if printLevel>1
            for n=1:nRxn0
                if fluxInConsistentRxnBool(n)

fprintf('%15s\t%-100s\n',modelOrig.rxns{n},modelOrig.rxnNames{n})
                    end
                end
            end
        end
        end
        %revise model size
        [nMet,nRxn]=size(model.S);

        %Recompute
        %Heuristically identify exchange reactions and metabolites
        exclusively involved in exchange reactions
        %finds the reactions in the model which export/import from the model
        %boundary i.e. mass unbalanced reactions
        %e.g. Exchange reactions
        %     Demand reactions
        %     Sink reactions

        model = findSExRxnInd(model,[],0);
        if printLevel>0
            fprintf('%s\n','-----end-----')
        end
    end
end
end

```

```

-----
#mets      #rxns
  5063      7330      totals.
  2123      2140      flux inconsistent reactions removed.
  2940      5190      remaining.
-----
1a_24_25VITD2Hm    1-alpha-Vitamin D-24,25-hydroxylase (D2)
1a_24_25VITD3Hm    1-alpha-Vitamin D-24,25-hydroxylase (D3)
  1a_25VITD2Hm     1-alpha,24R,25-Vitamin D-hydroxylase (D2)
  1a_25VITD3Hm     1-alpha,24R,25-Vitamin D-hydroxylase (D3)
  24_25DHVITD2t    24,25-Dihydroxyvitamin D2 transport from cytoplasm
  24_25DHVITD2tm   24,25-Dihydroxyvitamin D2 transport from mitochondria
  24_25VITD2Hm     24R-Vitamin D-25-hydroxylase (D2)
  25HVITD2t        25-hydroxyvitamin D2 transport from cytoplasm
  25HVITD2tin_m    25-hydroxyvitamin D2 transport in mitochondria
  25VITD2Hm        1-alpha-Vitamin D-25-hydroxylase (D2)
  25VITD3Hm        1-alpha-Vitamin D-25-hydroxylase (D3)
  34DHPHMT         3,4-Dihydroxyphenylacetate:amet O-methyltransferase
  3HPCOAHYD        3-hydroxyisobutyryl-Coenzyme A hydrolase
    3HPPD          3-hydroxypropionate dehydrogenase
  3HXKYNDCL        3-Hydroxykynurenamine decarboxy-lyase
  3HXKYNOXDA       3-Hydroxykynurenamine:oxygen oxidoreductase(deaminating)(flavin-containing)
  3M4HDXPAC        3-Methoxy-4-hydroxyphenylacetaldehyde:NAD+ oxidoreductase
  3MOXTYROX        3-Methoxytyramine:oxygen oxidoreductase (deaminating)
    3NTD71         3'-nucleotidase (AMP), lysosome
  42A12BOOX        4-(2-Aminoethyl)-1,2-benzenediol:oxygen oxidoreductase(deaminating)(flavin-containing)

```

| | |
|------------------|---|
| 4MPTNLtr | 4-methylpentanal transport (ER) |
| 5HOXINDACTOXm | 5-Hydroxyindoleacetaldehyde:NAD ⁺ oxidoreductase (mito) |
| 5HOXINOXDA | 5-Hydroxytryptamine:oxygen oxidoreductase(deaminating)(flavin-containing) |
| 5HTRPDOX | 5-Hydroxy-L-tryptophan:oxygen 2,3-dioxygenase (indole-decycling) |
| 5HXKYNDCL | 5-Hydroxykynurenamine decarboxy-lyase |
| 5HXKYNOXDA | 5-Hydroxykynurenamine:oxygen oxidoreductase(deaminating)(flavin-containing) |
| A_MANASE | alpha-mannosidase |
| A4GALTc | Lactosylceramide 4-alpha-galactosyltransferase |
| A4GNTlg | alpha 1,4-N-acetylglucosaminyltransferase, Golgi apparatus |
| ABUTt2rL | 4-aminobutyrate reversible transport in via proton symport (lysosome) |
| ACACT8p | acetyl-CoA acyltransferase (hexadecanoyl-CoA), peroxisomal |
| ACACT9p | acetyl-CoA acyltransferase (tetracosanoyl-CoA), peroxisomal |
| ACGSm | N-acetylglutamate synthase, mitochondrial |
| ACOATA | Acetyl-CoA ACP transacylase |
| ACODA | acetylornithine deacetylase |
| ACSOMT | S-Adenosyl-L-methionine:N-acetylserotonin O-methyltransferase |
| ACSRTNMT | S-Adenosyl-L-homocysteine:N-acetylserotonin O-methyltransferase |
| ACTg | acetate transport, Golgi apparatus |
| ADEt1 | adenine facilitated transport from lysosome |
| ADHAPTx | intracellular transport (peroxisome) |
| ADNt1 | adenosine facilitated transport from lysosome |
| ADPGLC | ADPglucose diphosphatase |
| ADPMAN | ADPmannose diphosphatase |
| ADPRDPM | ADPribose diphosphatase (mitochondrial) |
| ADSELK | adenylyl-selenate kinase |
| AGLPC | alkyl acylglycerol phosphocholine transferase |
| AGLPED | alkyl acyl glycerophosphoethanolamine desaturase |
| AGLPET | alkyl acylglycerol phosphoethanolamine transferase |
| AGLPH | alkyl glycerol phosphate hydrolase |
| AGLPR | alkyl glycerol phosphate reductase |
| AGLPT | alkyl glycerol phosphate acyltransferase |
| AGPex | alkyl glycerol phosphate transport |
| AGPRim | N-acetyl-g-glutamyl-phosphate reductase, irreversible, mitochondrial |
| AGPSx | alkylglycerone phosphate synthase |
| AHANDROSTANGLCte | glucuronidated compound transport |
| AHANDROSTANGLCtr | glucuronidated compound transport |
| AHCYStn | S-adenosyl-L-homocysteine nuclear transport |
| ALAt2rL | L-alanine reversible transport via proton symport (lysosome) |
| ALDD20x | aldehyde dehydrogenase (indole-3-acetaldehyde, NAD) |
| ALDD20xm | aldehyde dehydrogenase (indole-3-acetaldehyde, NAD), mitochondrial |
| ALKP | alkaline phosphatase |
| ALOX12 | Arachidonate 12-lipoxygenase |
| ALOX12R | Arachidonate 12-lipoxygenase R |
| ALOX15 | Arachidonate 15-lipoxygenase |
| AMACR2r | alpha-methylacyl-CoA racemase (reductase) |
| AMACRr | alpha-methylacyl-CoA racemase |
| AMETtn | S-adenosyl-L-methionine nuclear transport |
| AMPtr | AMP transporter, endoplasmic reticulum |
| AP4AH1 | Ap4A hydrolase, asymmetrically |
| APRTO2 | N-acetylputrescine: oxygen oxidoreductase (deaminating) |
| AQCOBALt | Aquacob(III)alamin uptake |
| ARTFR11 | R group artificial flux |
| ARTFR12 | R group artificial flux (C16:1) |
| ARTFR13 | R group artificial flux |
| ARTFR202 | R group artificial flux (C18:3, n-3) |
| ARTFR203 | R group artificial flux |
| ARTFR204 | R group artificial flux |
| ARTFR205 | R group artificial flux |
| ARTFR206 | R group artificial flux |
| ARTFR207 | R group artificial flux |
| ARTFR208 | R group artificial flux |
| ARTFR209 | R group artificial flux |
| ARTFR210 | R group artificial flux |
| ARTFR211 | R group artificial flux |

| | |
|--------------|---|
| ARTFR212 | R group artificial flux |
| ARTFR213 | R group artificial flux |
| ARTFR31 | R group artificial flux |
| ARTFR32 | R group artificial flux |
| ARTFR33 | R group artificial flux |
| ARTFR34 | R group artificial flux |
| ARTFR41 | R group artificial flux |
| ARTFR42 | R group artificial flux |
| ARTFR43 | R group artificial flux |
| ARTFR44 | R group artificial flux |
| ARTFR45 | R group artificial flux |
| ARTFR46 | R group artificial flux |
| ARTFR51 | R group artificial flux |
| ARTFR52 | R group artificial flux |
| ARTFR53 | R group artificial flux |
| ARTFR54 | R group artificial flux |
| ARTFR55 | R group artificial flux |
| ARTFR56 | R group artificial flux |
| ARTFR57 | R group artificial flux |
| ARTFR61 | R group artificial flux |
| ARTPLM1 | R group to palmitate conversion |
| ARTPLM1m | R group to palmitate conversion |
| ARTPLM2 | R group to palmitate conversion |
| ARTPLM2m | R group to palmitate conversion |
| ARTPLM3 | R group to palmitate conversion |
| ARTPLM3m | R group to palmitate conversion |
| BAMPPALDOXm | beta-Aminopropion aldehyde:NAD+ oxidoreductase (m) |
| BBHOX | 4-Trimethylammonibutanoate,2-oxoglutarate:oxygen oxidoreductase (3-hydroxylating) |
| BDG2HCGHD | beta-D-Glucosyl-2-coumarinate glucohydrolase |
| BTnt2m | Biotin reversible transport via proton symport, mitochondria |
| BZt | benzoate transport (diffusion) |
| BZtr | Benzene transporter, endoplasmic reticulum |
| C2M26DCOAHLM | cis-2-Methyl-5-isopropylhexa-2,5-dienoyl-CoA hydro-lyase (m) |
| C2M26DCOAHLx | cis-2-Methyl-5-isopropylhexa-2,5-dienoyl-CoA hydro-lyase (x) |
| CBL2OR | NADH:cob(III)alamine oxidoreductase |
| CBL2tm | Cob(II)alamine transport, mitochondrial |
| CBLATm | cob(I)alamin adenosyltransferase, mitochondrial |
| CBPPer | Carbamoyl phosphate phosphotransferase, endoplasmic reticulum |
| CBPter | carbamoyl phosphate transport, endoplasmic reticulum |
| CBR1 | Carbonyl reductase [NADPH] 1 |
| CCA_D3t | Calcitroic acid transport from cytosol |
| CCA_D3tm | Calcitroic acid transport from mitochondria |
| CHSTEROLtg | cholesterol efflux (ATP depedent), golgi |
| CHTNASE | chitinase |
| CITMCOAHm | L-Citramalyl-CoA hydro-lyase, mitochondrial |
| CITMCOALm | L-Citramalyl-CoA pyruvate-lyase |
| CLPNDCPT1 | carnitine O-palmitoyltransferase |
| CLPNDCPT2 | carnitine transferase |
| CLPNDCRnt | transport into the mitochondria (carnitine) |
| CO2tg | CO2 Golgi transport |
| CO2tn | CO2 nuclear transport via diffusion |
| COKECBESr | Carboxylesterase (cocaine) (er) |
| CPCTDTX | choline-phosphate cytidyltransferase |
| CRTNsyn | Creatinine synthase |
| CRTSLtr | cortisol intracellular transport |
| CRTSTRNtr | corticosterone intracellular transport |
| CSPG_At | chondroitin sulfate A transport, golgi to extracellular |
| CSPG_Bt | chondroitin sulfate B transport, golgi to extracellular |
| CSPG_Ct | chondroitin sulfate C transport, golgi to extracellular |
| CSPG_Dt | chondroitin sulfate D transport, golgi to extracellular |
| CSPG_Et | chondroitin sulfate E transport, golgi to extracellular |
| CYOOm2 | cytochrome c oxidase, mitochondrial Complex IV |
| CYSLYSL | L-Cystine Lysteine-lyase (deaminating) |
| CYSTAm | cysteine transaminase (mitochondrial) |

| | |
|-----------------------------|---|
| CYTDt1 | Cytidine facilitated transport from lysosome |
| DALAt2rL | D-alanine transport via proton symport (lysosome) |
| DARGOp | D-arginine oxidase, perixosomal |
| DASCBH | L-Dehydroascorbate lactonohydrolase |
| DCIm | dodecenoyl-Coenzyme A delta isomerase |
| DCK1m | Deoxycytidine kinase, mitochondrial (ATP) |
| DEDOLP1_L | dehydrodolichol diphosphate phosphatase (liver) |
| DEDOLP1_U | dehydrodolichol diphosphate phosphatase (uterus) |
| DEDOLP2_L | dehydrodolichol phosphate phosphatase (liver) |
| DEDOLP2_U | dehydrodolichol phosphate phosphatase (uterus) |
| DEDOLR_L | dehydrodolichol reductase (liver) |
| DEDOLR_U | dehydrodolichol reductase (uterus) |
| DHAPA | dihydroxyacetone phosphate acyltransferase |
| DHAPAx | dihydroxyacetone phosphate acyltransferase |
| DHEAStr | dheas intracellular transport |
| D_LACTm | D-lactate transport, mitochondrial |
| DM_m_em_3gacpail_prot_hs_r_ | DM m(em)3gacpail prot hs(r) |
| DMHPTCRNCP1 | carnitine fatty-acyl transferase |
| DNAMTn | DNA (cytosine-5-)-methyltransferase, nucleus |
| DNAMTSEn | DNA (cytosine-5-)-methyltransferase, nucleus |
| DOGULND1 | 2,3-dioxo-L-gulonate decarboxylase (L-lyxonate-forming) |
| DOGULND2 | 2,3-dioxo-L-gulonate decarboxylase (L-xylonate-forming) |
| DOGULNO1 | 2,3-dioxo-L-gulonate:hydrogen peroxide oxireductase |
| DOGULNO2 | 2,3-dioxo-L-gulonate:hydrogen peroxide oxireductase |
| DOPAMT | Dopamine:amet O-methyltransferase |
| DORNOp | D-ornithine oxidase, perixosomal |
| DPROOp | D-proline oxidase, perixosomal |
| ECGISOr | Ecgonine isomerase (ER) |
| ECOAHLx | 3-hydroxyacyl-CoA dehydratase (3-hydroxybutanoyl-CoA) (perioxisome) |
| EGMESTr | ecgonine methyl esterase (ER) |
| EHGLAT | L-erythro-4-Hydroxyglutamate:2-oxoglutarate aminotransferase |
| ENGASE | endo-beta-N-acetylglucosaminidase |
| ENGASE2 | endo-beta-N-acetylglucosaminidase |
| ENMAN1g | Endomannosidase (glc1man-producing), Golgi apparatus |
| ENMAN2g | Endomannosidase (glc2man-producing), Golgi apparatus |
| ENMAN3g | Endomannosidase (glc3man-producing), Golgi apparatus |
| ENMAN4g | Endomannosidase (m6masnC-producing), Golgi apparatus |
| ENMAN5g | Endomannosidase (m6masnB2-producing), Golgi apparatus |
| ENMAN6g | Endomannosidase (m5masnB1-producing), Golgi apparatus |
| EPCTX | ethanolamine-phosphate cytidylyltransferase |
| ESTRIOLGLCte | glucuronidated compound transport |
| ESTRIOLGLCtr | glucuronidated compound transport |
| ESTRIOLtr | estriol intracellular transport |
| EX_2425dhvitd2(e) | 24R,25-Dihydroxyvitamin D2 exchange |
| EX_25hvitd2(e) | 25-Hydroxyvitamin D2 exchange |
| EX_ahandrostanglc(e) | Etiocholan-3alpha-ol-17-one 3-glucuronide exchange |
| EX_aqcobal(e) | Aquacob(III)alamin exchange |
| EX_bz(e) | Benzoate exchange |
| EX_ca2(e) | Calcium exchange |
| EX_cca_d3(e) | Calcitroic acid (D3) exchange |
| EX_estriolglc(e) | 16-Glucuronide-estriol exchange |
| EX_hom_L(e) | L-Homoserine exchange |
| EX_k(e) | K+ exchange |
| EX_lipoate(e) | Lipoate exchange |
| EX_nal(e) | exchange reaction for Sodium |
| EX_nifedipine(e) | nifedipine exchange |
| EX_peplys(e) | Peptidyl-L-lysine exchange |
| EX_phyQ(e) | Phylloquinone exchange |
| EX_pro_D(e) | D-Proline exchange |
| EX_sel(e) | Selenate exchange |
| EX_ser_D(e) | D-Serine exchange |
| EX_vitd2(e) | Vitamin D2 exchange |
| EX_whtststerone(e) | w hydroxy testosterone exchange |
| EX_xolest_hs(e) | cholesterol ester exchange |

| | |
|----------------|--|
| FA120ACPH | fatty-acyl-ACP hydrolase |
| FA140ACPH | fatty-acyl-ACP hydrolase |
| FA141ACPH | fatty-acyl-ACP hydrolase |
| FA160ACPH | fatty-acyl-ACP hydrolase |
| FA161ACPH | fatty-acyl-ACP hydrolase |
| FA180ACPH | fatty-acyl-ACP hydrolase |
| FA181ACPH | fatty-acyl-ACP hydrolase |
| FA1821ACPH | fatty-acyl-ACP hydrolase |
| FA1822ACPH | fatty-acyl-ACP hydrolase |
| FA182ACPH | fatty-acyl-ACP hydrolase |
| FORtrn | Formate transport, nuclear |
| FRTT | farnesyltranstransferase |
| FT | farnesyltranstransferase (trans,trans,cis-geranylgeranyl diphosphate-generating) |
| G1M6MASNB1terg | g1m6masnB1 endoplasmic reticulum to Golgi transport |
| G1M7MASNBterg | g1m7masnC endoplasmic reticulum to Golgi transport |
| G1M7MASNCterg | g1m7masnC endoplasmic reticulum to Golgi transport |
| G1M8MASNterg | g1m8masn transport from endoplasmic reticulum to Golgi apparatus |
| G1PTT | glucose-1-phosphate thymidyltransferase |
| G2M8MASNterg | g2m8masn transport from endoplasmic reticulum to Golgi apparatus |
| G3M8MASNterg | g3m8masn transport from endoplasmic reticulum to Golgi apparatus |
| GALNACT1g | UDPGal-chondroitin acetylgalactosaminyltransferase I, Golgi |
| GALNACT2g | uridine diphosphoacetylgalactosamine-chondroitin acetylgalactosaminyltransferase II, Golgi |
| GALNACT3g | uridine diphosphoacetylgalactosamine-chondroitin acetylgalactosaminyltransferase II, Golgi |
| GALNACT4g | uridine diphosphoacetylgalactosamine-chondroitin acetylgalactosaminyltransferase II, Golgi |
| GALNACT5g | uridine diphosphoacetylgalactosamine-chondroitin acetylgalactosaminyltransferase II, Golgi |
| GALOR | D-Galactose:NADP+ 1-oxidoreductase |
| GALT2g | UDP-D-galactose:galactosylxylose galactosyltransferase, Golgi apparatus |
| GALTg | UDP-D-galactose:D-xylose galactosyltransferase, Golgi apparatus |
| GAO1 | Ganglioside O-acetylation |
| GAO2 | Ganglioside O-acetylation |
| GCALDDm | Glycolaldehyde dehydrogenase, mitochondrial |
| GGT_L | geranylgeranyltransferase (liver) |
| GGT_U | geranylgeranyltransferase (uterus) |
| GHMT3 | glycine hydroxymethyltransferase |
| GHMT3m | glycine hydroxymethyltransferase, mitochondrial |
| GK1m | guanylate kinase (GMP:ATP), mitochondrial |
| GLACO | D-Glucuronolactone:NAD+ oxidoreductase |
| GLACOm | D-Glucuronolactone:NAD+ oxidoreductase, mitochondrial |
| GLCAE1g | chondroitin-glucuronate 5-epimerase |
| GLCAE2g | heparosan-N-sulfate-glucuronate 5-epimerase |
| GLCAT2g | chondroitin glucuronyltransferase II, Golgi apparatus |
| GLCAT3g | chondroitin glucuronyltransferase II, Golgi apparatus |
| GLCAT4g | chondroitin glucuronyltransferase II, Golgi apparatus |
| GLCAT5g | chondroitin glucuronyltransferase II, Golgi apparatus |
| GLCAT6g | heparan glucuronyltransferase II |
| GLCAT7g | heparan glucuronyltransferase II |
| GLCAT8g | heparan glucuronyltransferase II |
| GLCAT9g | heparan glucuronyltransferase II |
| GLCATg | UDP-D-glucuronate:galactosylgalactosylxylose glucuronosyltransferase, Golgi apparatus |
| GLCNACDASg | GlcNAc N-deacetylase / N-sulfotransferase |
| GLCNACT1g | alpha-N-acetylglucosaminyltransferase I, Golgi apparatus |
| GLCNACT2g | alpha-N-acetylglucosaminyltransferase II |
| GLCNACT3g | alpha-N-acetylglucosaminyltransferase II |
| GLCNACT4g | alpha-N-acetylglucosaminyltransferase II |
| GLCNACT5g | alpha-N-acetylglucosaminyltransferase II |
| GLYCLTDym | Glycolate dehydrogenase (NADP), mitochondrial |
| GLYOXm | hydroxyacylglutathione hydrolase, mitochondrial |
| GLYt2rL | glycine reversible transport via proton symport (lysosome) |
| GPAMm_hs | glycerol-3-phosphate acyltransferase |
| GSNKm | guanosine kinase (mitochondrial) |
| GSNt1 | guanosine facilitated transport from lysosome |
| GSNtm | guanosine facilitated transport in mitochondria |
| GTPCI | GTP cyclohydrolase I |
| GTPCIn | GTP cyclohydrolase I, nuclear |

| | |
|-------------|---|
| GTPtn | GTP diffusion in nucleus |
| H2CO3Dm | carboxylic acid dissociation |
| H8MTER_L | H8 mannosyltransferase, endoplasmic reticulum |
| H8MTER_U | H8 mannosyltransferase, endoplasmic reticulum |
| HACD1x | 3-hydroxyacyl-CoA dehydrogenase (acetoacetyl-CoA) (peroxisome) |
| HEXCCT1 | carnitine O-palmitoyltransferase |
| HEXCCT2 | carnitine transferase |
| HEXCCRnt | transport into the mitochondria (carnitine) |
| HISTASE | Histaminase |
| HMGCOARr | Hydroxymethylglutaryl CoA reductase (ir) |
| HPYRDCm | hydroxypyruvate decarboxylase, mitochondria |
| HSD3B13 | 3 beta-hydroxysteroid dehydrogenase/delta 5-->4-isomerase type I |
| HSPGt | heparan sulfate transport, golgi to extracellular |
| HXANTl | hypoxanthine facilitated transport from lysosome |
| IMACTD | Imidazole acetaldehyde dehydrogenase |
| IMACTD_m | Imidazole acetaldehyde dehydrogenase (mito) |
| INSKm | inosine kinase, mitochondrial |
| INSTl | inosine facilitated transport from lysosome |
| INSTm | inosine facilitated transport in mitochondria |
| IPDPtr | Isopentenyl diphosphate transport (ER) |
| Kt3g | potassium transport via proton antiport |
| LACZly | b-galactosidase, lysosomal |
| LCADi_Dm | lactaldehyde dehydrogenase, mitochondrial |
| LCADim | lactaldehyde dehydrogenase, mitochondrial |
| LCTStl | lactose transport from cytosol to lysosome (via autophagocytosis) |
| LCYSTATm | L-Cysteate:2-oxoglutarate aminotransferase, mitochondrial |
| LDH_Lm | L-lactate dehydrogenase |
| LEUKTRB4tr | leukotriene intracellular transport |
| LGNCCT1 | carnitine O-palmitoyltransferase |
| LGNCCT2 | transport into the mitochondria (carnitine) |
| LGNCRRnt | transport into the mitochondria (carnitine) |
| LIPoti | Lipoate transport via sodium symport |
| L_LACTcm | L-lactate transport via diffusion (cytosol to mitochondria) |
| LNS14DM | cytochrome P450 lanosterol 14-alpha-demethylase (NADP) |
| LS3 | Lumisterol 3 formation |
| LTDCL | L-Tryptophan decarboxy-lyase |
| LYSMTF1n | histone-lysine N-methyltransferase, nuclear |
| LYSMTF2n | histone-lysine N-methyltransferase, nuclear |
| LYSMTF3n | histone-lysine N-methyltransferase, nuclear |
| M4ATAer | M4A transamidase, endoplasmic reticulum |
| M4BET2er | M4B phosphoethanolaminy transferase, endoplasmic reticulum |
| MALTly | alpha-glucosidase, lysosomal |
| MAN1_6Bler | mannosidase I, endoplasmic reticulum (glm6masnB1-producing) |
| MAN1_7Ber | mannosidase I, endoplasmic reticulum (glm7masnB-producing) |
| MAN2_6Bler | mannosidase II, endoplasmic reticulum (glm6masnB1-producing) |
| MAN2_7Cer | mannosidase II, endoplasmic reticulum (glm7masnC-producing) |
| MAOLNOR | monoamine oxidase (L-Normetanephine) |
| MCDp | Malonyl-CoA Decarboxylase peroxisomal |
| MCOATA | Malonyl-CoA-ACP transacylase |
| MCOATAm | Malonyl-CoA-ACP transacylase, mitochondrial |
| MELATN23DOX | Melatonin:oxygen 2,3-dioxygenase (indole-decyclizing) |
| MEOHtr | Methanol transporter, endoplasmic reticulum |
| MESCOALm | Mesaconyl-CoA pyruvate-lyase |
| MGACONm | methylglutaconase, mitochondrial |
| MI13456PK | inositol-1,3,4,5,6-pentakisphosphate 2-kinase |
| MI13456Ptn | inositol 1,3,4,5,6-pentakisphosphate nuclear transport (diffusion) |
| MI1345PKn | inositol-1,3,4,5-triphosphate 6-kinase, nucleus |
| MI1346PKn | inositol-1,3,4,6-tetrakisphosphate 5-kinase, nucleus |
| MI1346Ptn | 1D-myo-Inositol 1,3,4,6-tetrakisphosphate nuclear transport (diffusion) |
| MI134PK | inositol-1,3,4-trisphosphate 6-kinase |
| MI1456PKn | inositol-1,4,5,6- tetrakisphosphate 3-kinase, nucleus |
| MI145P6Kn | inositol-1,4,5-triphosphate 6-kinase, nucleus |
| MI145PKn | inositol-1,4,5-trisphosphate 3-kinase, nucleus |
| MI3456PK | inositol-3,4,5,6-tetrakisphosphate 1-kinase |

| | |
|--------------|---|
| MICITDr | 2-methylisocitrate dehydratase |
| MINOHPtn | inositol hexakisphosphate nuclear transport (diffusion) |
| MLTG1 | Maltodextrin glucosidase (maltotriose) |
| MLTG1ly | Maltodextrin glucosidase (maltotriose), lysosome |
| MMCD | Methylmalonyl-CoA decarboxylase |
| MMCDp | Methylmalonyl-CoA decarboxylase, peroxisomal |
| NABTNO | N4-Acetylaminobutanol:NAD ⁺ oxidoreductase |
| NABTNOm | N4-Acetylaminobutanol:NAD ⁺ oxidoreductase (m) |
| NADK | NAD kinase |
| NADPN | NADP nucleosidase |
| Nat3_1g | sodium proton antiporter (H:NA is 1:1) |
| NDPK10m | nucleoside-diphosphate kinase (ATP:dIDP), mitochondrial |
| NDPK2m | nucleoside-diphosphate kinase (ATP:UDP), mitochondrial |
| NDPK9m | nucleoside-diphosphate kinase (ATP:IDP), mitochondrial |
| NIFEDIPINete | xenobiotic transport |
| NMNATm | nicotinamide-nucleotide adenyllyltransferase, mitochondrial |
| NMPTRCOX | N-Methylputrescine:oxygen oxidoreductase (deaminating) |
| NNATm | nicotinate-nucleotide adenyllyltransferase, mitochondrial |
| NRVNCCPT1 | carnitine O-palmitoyltransferase |
| NRVNCCPT2 | carnitine transferase |
| NRVNCCRnt | transport into the mitochondria (carnitine) |
| NTD12 | 5'-nucleotidase (dIMP) |
| NTD21 | 5'-nucleotidase (UMP), lysosome |
| NTD2m | 5'-nucleotidase (UMP), mitochondrial |
| NTD31 | 5'-nucleotidase (dCMP), lysosomal |
| NTD41 | 5'-nucleotidase (CMP), lysosome |
| NTD51 | 5'-nucleotidase (dTMP), lysosomal |
| NTD61 | 5'-nucleotidase (dAMP), lysosome |
| NTD71 | 5'-nucleotidase (AMP), lysosome |
| NTD81 | 5'-nucleotidase (dGMP), lysosomal |
| NTD91 | 5'-nucleotidase (GMP), lysosome |
| NTMELYStner | protein trimethyl lysine transport (nucleus to ER) |
| NTPP10 | Nucleoside triphosphate pyrophosphorylase (ditp) |
| NTPP11 | Nucleoside triphosphate pyrophosphorylase (xtp) |
| NTPP9 | Nucleoside triphosphate pyrophosphorylase (itp) |
| P4503A4 | cytochrome P450 3A4 |
| P4503A43r | cytochrome p450 P450 3A43 |
| P4504B1r | cytochrome P450 4B1 |
| P4504F121r | cytochrome p450 4F12/4F2 |
| P4504F122r | cytochrome p450 4F12/4F2 |
| P4504F81r | cytochrome p450 4F8 |
| P450LTB4r | cytochrome p450 leukotriene B4 |
| PCLYSOX | Procollagen-lysine 1, 2-oxoglutarate 5-dioxygenase |
| PDE1g | 3',5'-cyclic-nucleotide phosphodiesterase, Golgi |
| PDE4g | 3',5'-cyclic-nucleotide phosphodiesterase, Golgi |
| PE_HStg | phosphatidylethanolamine scramblase |
| PEGONCOATr | Pseudoecgonine CoA transferase (ER) |
| PEPLYStn | peptide (lysine) nuclear transport via diffusion |
| PGDIr | Prostaglandin-H2 D-isomerase [Precursor] |
| PGESr | Prostaglandin E synthase |
| PGLYCP | Phosphoglycolate phosphatase |
| PHETA1 | phenylalanine transaminase |
| PHETA1m | phenylalanine transaminase (m) |
| PI45PLCn | phosphatidylinositol 4,5-bisphosphate phospholipase C, nucleus |
| PI4P3Ker | phosphatidylinositol 4-phosphate 3-kinase, endoplasmic reticulum |
| PI5P3Ker | phosphatidylinositol-5-phosphate 3-kinase, endoplasmic reticulum |
| Pit2m | phosphate transporter, mitochondrial |
| PLA2 | phospholipase A2 |
| PLYSPSer | protein lysine peptidase (endoplasmic reticulum) |
| PMI12346PH | 5-diphosphoinositol-1,2,3,4,6-pentakisphosphate diphosphohydrolase |
| PMI12346PHn | 5-diphosphoinositol-1,2,3,4,6-pentakisphosphate diphosphohydrolase, nucleus |
| PMI1346PH | diphosphoinositol-1,3,4,6-tetrakisphosphate diphosphohydrolase |
| PMI1346PHn | diphosphoinositol-1,3,4,6-tetrakisphosphate diphosphohydrolase, nucleus |
| PNTKm | pantothenate kinase (mitochondrial) |

| | |
|----------------|--|
| PPA2 | inorganic triphosphatase |
| PPA2m | inorganic triphosphatase, mitochondrial |
| PPMI12346Ptn | 5-diphosphatidylinositol pentakisphosphate nuclear transport (diffusion) |
| PPMI1346Ptn | diphosphatidylinositol tetrakisphosphate nuclear transport (diffusion) |
| PPOR | Phenylpyruvate:oxygen oxidoreductase (hydroxylating,decarboxylating) |
| PPPItn | Inorganic triphosphate transport through nuclear pore |
| PROAKGOX1r | L-Proline,2-oxoglutarate:oxygen oxidoreductase (4-hydroxylating) (ER) |
| PRODt2r | D-proline reversible transport via proton symport |
| PRODt2rL | D-proline reversible transport via proton symport (lysosome) |
| PROt2rL | L-proline reversible transport via proton symport (lysosome) |
| PROtm | L-proline transport, mitochondrial |
| PRPNCOAHYDx | Propenoyl-CoA hydrolase (x) |
| PS_HSter | phosphatidylserine scramblase |
| PS_HStg | phosphatidylserine scramblase |
| PTE2x | peroxisomal acyl-CoA thioesterase |
| PTE5x | peroxisomal acyl-CoA thioesterase |
| PTHPS | 6-pyruvoyltetrahydropterin synthase |
| PTHPSn | 6-pyruvoyltetrahydropterin synthase, nuclear |
| PTRCAT1 | Putrescine acetyltransferase |
| PYAM5Ptm | Pyridoxamine 5'-phosphate transport via diffusion, mitochondrial |
| PYDX5Ptm | Pyridoxal 5'-phosphate transport via diffusion, mitochondrial |
| PYLALDOX | Perillyl aldehyde:NAD+ oxidoreductase |
| PYLALDOXm | Perillyl aldehyde:NAD+ oxidoreductase (m) |
| QUILSYN | Quinolate Synthase (Eukaryotic) |
| RAtn | Retinoate transport, nuclear |
| RBK_D | D-ribulokinase |
| RETNCOA | Retinoyl CoA formation |
| RTOT_2 | R total flux 2 position |
| RTOT_3 | R total flux 3 position |
| RTOT1 | R total flux |
| RTOT2 | R total flux |
| RTOT3 | R total flux |
| RTOT4 | R total flux |
| RTOT5 | R total flux |
| RTOT6 | R total flux |
| RTOTAL2CRNCPT1 | carnitine fatty-acyl transferase |
| RTOTAL2CRNCPT2 | R group transport into the mitochondria |
| RTOTAL2CRNt | R group transport into the mitochondria |
| RTOTAL3CRNCPT1 | carnitine fatty-acyl transferase |
| RTOTAL3CRNCPT2 | R group transport into the mitochondria |
| RTOTAL3CRNt | R group transport into the mitochondria |
| RTOTALCRNCPT1 | carnitine fatty-acyl transferase |
| RTOTALCRNCPT2 | R group transport into the mitochondria |
| RTOTALCRNt | R group transport into the mitochondria |
| Rtotaltp | fatty acid intracellular transport |
| S2T1g | chondroitin 2-sulfotransferase, Golgi |
| S2T2g | chondroitin 2-sulfotransferase, Golgi |
| S2T3g | uronyl 2-sulfotransferase, Golgi |
| S2T4g | uronyl 2-sulfotransferase, Golgi |
| S3T1g | heparin-glucosamine 3-O-sulfotransferase |
| S3T2g | heparin-glucosamine 3-O-sulfotransferase |
| S3T3g | heparin-glucosamine 3-O-sulfotransferase |
| S4T1g | chondroitin 4-sulfotransferase, Golgi apparatus |
| S4T2g | chondroitin 4-sulfotransferase, Golgi apparatus |
| S4T3g | chondroitin 4-sulfotransferase, Golgi apparatus |
| S4T4g | chondroitin 4-sulfotransferase, Golgi apparatus |
| S4T5g | chondroitin 4-sulfotransferase, Golgi apparatus |
| S4T6g | chondroitin 4-sulfotransferase, Golgi apparatus |
| S6T19g | chondroitin 6-sulfotransferase, Golgi apparatus |
| S6T20g | chondroitin 6-sulfotransferase, Golgi apparatus |
| S6T21g | chondroitin 6-sulfotransferase, Golgi apparatus |
| S6T22g | chondroitin 6-sulfotransferase, Golgi apparatus |
| S6T23g | chondroitin 6-sulfotransferase, Golgi apparatus |
| S6T24g | chondroitin 6-sulfotransferase, Golgi apparatus |

| | |
|--------------|---|
| S6T25g | heparan sulfate 6-sulfotransferase, Golgi apparatus |
| SALMCOM | S-Adenosyl-L-methionine:catechol O-methyltransferase |
| SARCOXp | sarcosine oxidase, peroxisomal |
| SARCStp | Sarcosine transport (peroxisomal) |
| SEAHCYSHYD | Se-Adenosylselenohomocysteine hydrolase |
| SEAHCYStn | Se-adenosyl-seleno-L-homocysteine nuclear transport |
| SEASMETtn | Se-adenosyl-seleno-L-methionine nuclear transport |
| SELADT | selenate adenylyltransferase |
| SELCYSLY | selenocysteine lyase |
| SELCYSLY2 | selenocysteine lyase |
| SELCYSTGL | selanocystathionine g-lyase |
| SELCYSTS | selanocystathionine beta-synthase |
| SELMETAT | selenomethionine adenosyltransferase |
| SELNPS | Selenophosphate synthase |
| SElt4_3 | selenate transport via sodium symport |
| SGPL1lr | Sphingosine-1-phosphate lyase 1 |
| SIAASE | sialidase |
| SLDxm | L-sulfolactate dehydrogenase (NAD+), mitochondrial |
| SOAT1l | sterol O-acyltransferase (acyl-Coenzyme A: cholesterol acyltransferase) 1 |
| SOAT1lr | sterol O-acyltransferase (acyl-Coenzyme A: cholesterol acyltransferase) 1 |
| SOAT12 | sterol O-acyltransferase (acyl-Coenzyme A: cholesterol acyltransferase) 1 |
| SOAT12r | sterol O-acyltransferase (acyl-Coenzyme A: cholesterol acyltransferase) 1 |
| SPR | sepiapterin reductase |
| SPRn | sepiapterin reductase, nuclear |
| SRTN23OX | 5-Hydroxytryptamine:oxygen 2,3-dioxygenase (indole-decyclizing) |
| SRTNACT | Acetyl-CoA:aralkylamine N-acetyltransferase |
| SRTNMTX | S-Adenosyl-L-methionine:amine N-methyltransferase (srtn) |
| STS1r | Steryl-sulfatase |
| STS2r | Steryl-sulfatase |
| T2M26DCOAHlm | trans-2-Methyl-5-isopropylhexa-2,5-dienoyl-CoA hydro-lyase (m) |
| T2M26DCOAHLx | trans-2-Methyl-5-isopropylhexa-2,5-dienoyl-CoA hydro-lyase (x) |
| T4HCINNOX | 4-Coumarate:oxygen oxidoreductase |
| TDPDRE | dTDP-4-dehydrorhamnose 3,5-epimerase |
| TDPDRR | dTDP-4-dehydrorhamnose reductase |
| TDPGDH | dTDPglucose 4,6-dehydratase |
| TETPENT3CPT1 | carnitine O-palmitoyltransferase |
| TETPENT3CPT2 | carnitine transferase |
| TETPENT3CRNt | transport into the mitochondria (carnitine) |
| TETPENT6CPT1 | carnitine O-palmitoyltransferase |
| TETPENT6CPT2 | carnitine transferase |
| TETPENT6CRNt | transport into the mitochondria (carnitine) |
| TETTET6CPT1 | carnitine O-palmitoyltransferase |
| TETTET6CPT2 | carnitine transferase |
| TETTET6CRNt | transport into the mitochondria (carnitine) |
| THMt2m | Thiamine transport in via proton symport, mitochondrial |
| THRS | threonine synthase |
| THYMDt1 | thymidine facilitated transport from lysosome |
| TMABADH | 4-trimethylaminobutyraldehyde dehydrogenase |
| TMLYSOX | trimethyllysine dioxygenase |
| TMLYSter | trimethyl-L-lysine transport (ER to cytosol) |
| TRDRm | thioredoxin reductase (NADPH) |
| TREH | alpha,alpha-trehalase |
| TRYPTAOX | Tryptamine:oxygen oxidoreductase(deaminating)(flavin-containing) |
| TS3 | Tachysterol 3 formation |
| UDPGAlt2g | UDPGalactose transport (Golgi) |
| UDPGLCatg | UDPGlcA Golgi transport via UMP antiport |
| UDPGLCtg | UDP-Glc Golgi transport via CMP antiport |
| UDPGLDCg | UDP-D-glucuronate decarboxylase, Golgi apparatus |
| UDPXYLter | UDP-Xyl endoplasmic reticular transport via CMP antiport |
| UDPXYLtg | UDP-Xyl Golgi transport via CMP antiport |
| UGALNACter | UDP-GalNAc endoplasmic reticulum transport via CMP antiport |
| UGT1A7r | UDP-glucuronosyltransferase 1-10 precursor, microsomal |
| UGT1A8r | UDP-glucuronosyltransferase 1-10 precursor, microsomal |
| UMPKm | UMP kinase (mitochondrial, ATP) |

| | |
|----------------|--|
| Uritl | uridine facilitated transport from lysosome |
| Uritm | uridine facilitated transport in mitochondria |
| UTPtn | UTP diffusion in nucleus |
| VITD2Hm | Vitamin D-25-hydroxylase (D2) |
| VITD2t | Vitamin D2 release |
| VITD2tm | Vitamin D2 transport from mitochondria |
| VITD3Hm | Vitamin D-25-hydroxylase (D3) |
| VITD3tm | Vitamin D3 transport from mitochondria |
| WHTSTSTERONete | omega hydroxy testosterone transport |
| XOL7AH2tr | lipid, flip-flop intracellular transport |
| XOLDIOLONetm | lipid, flip-flop intracellular transport |
| XOLESTte | cholesterol ester transporter |
| XOLTRIOltr | lipid, flip-flop intracellular transport |
| XSERTg | Xyl-L-Ser (protein) transport from endoplasmic reticulum to Golgi apparatus |
| XYLTer | UDP-xylose:protein xylosyltransferase, endoplasmic reticulum |
| EX_HC01440(e) | Exchange of 3-Keto-beta-D-galactose |
| EX_HC01441(e) | Exchange of Lactose-6P |
| EX_HC01446(e) | Exchange of 3-Ketolactose |
| EX_HC01577(e) | Exchange of gamma-Glutamyl-beta-cyanoalanine |
| EX_HC01700(e) | Exchange of gamma-Glutamyl-3-aminopropionitrile |
| EX_HC02160(e) | Exchange of GM2-pool |
| EX_HC02161(e) | Exchange of GM1-pool |
| r0001 | Virtual reaction/potential definition |
| r0023 | NADH:ferricytochrome-b5 oxidoreductase Aminosugars metabolism EC:1.6.2.2 |
| r0024 | N-(omega)-Hydroxyarginine,NADPH:oxygen oxidoreductase (nitric-oxide-forming) Arginine a |
| r0120 | GTP 7,8-8,9-dihydrolase Folate biosynthesis EC:3.5.4.16 |
| r0121 | |
| r0205 | sn-Glycerol-3-phosphate:(acceptor) 2-oxidoreductase Glycerophospholipid metabolism EC:1 |
| r0220 | Propinol adenylate:CoA ligase (AMP-forming) Propanoate metabolism EC:6.2.1.17 EC:6.2.1. |
| r0221 | Propinol adenylate:CoA ligase (AMP-forming) Propanoate metabolism EC:6.2.1.17 |
| r0318 | Propanoate:CoA ligase (AMP-forming) Propanoate metabolism EC:6.2.1.1 EC:6.2.1.17 |
| r0319 | Propanoate:CoA ligase (AMP-forming) Propanoate metabolism EC:6.2.1.1 EC:6.2.1.17 |
| r0366 | [Acyl-carrier-protein] 4-pantetheine-phosphohydrolase Pantothenate and CoA biosynthesis |
| r0368 | CoA:apo-[acyl-carrier-protein] pantetheinephosphotransferase Pantothenate and CoA biosyn |
| r0380 | Lactose 6-phosphate galactohydrolase Galactose metabolism EC:3.2.1.23 |
| r0402 | Tetrahydrobiopterin:NADP+ oxidoreductase Folate biosynthesis EC:1.1.1.153 |
| r0430 | Palmitoyl-CoA:L-carnitine O-palmitoyltransferase Fatty acid metabolism EC:2.3.1.21 |
| r0431 | Palmitoyl-CoA:L-carnitine O-palmitoyltransferase Fatty acid metabolism EC:2.3.1.21 |
| r0432 | Palmitoyl-CoA:L-carnitine O-palmitoyltransferase Fatty acid metabolism EC:2.3.1.21 |
| r0433 | Palmitoyl-CoA:L-carnitine O-palmitoyltransferase Fatty acid metabolism EC:2.3.1.21 |
| r0438 | Palmitoyl-CoA:L-carnitine O-palmitoyltransferase Fatty acid metabolism EC:2.3.1.21 |
| r0439 | Palmitoyl-CoA:L-carnitine O-palmitoyltransferase Fatty acid metabolism EC:2.3.1.21 |
| r0440 | Palmitoyl-CoA:L-carnitine O-palmitoyltransferase Fatty acid metabolism EC:2.3.1.21 |
| r0444 | Palmitoyl-CoA:L-carnitine O-palmitoyltransferase Fatty acid metabolism EC:2.3.1.21 |
| r0445 | Palmitoyl-CoA:L-carnitine O-palmitoyltransferase Fatty acid metabolism EC:2.3.1.21 |
| r0446 | Palmitoyl-CoA:L-carnitine O-palmitoyltransferase Fatty acid metabolism EC:2.3.1.21 |
| r0465 | L-Histidine:4-aminobutanoate ligase (AMP-forming) Urea cycle and metabolism of amino gr |
| r0466 | alpha-Aminobutyryl histidine hydrolase Urea cycle and metabolism of amino groups EC:3.4 |
| r0510 | steroyl-CoA,hydrogen-donor:oxygen oxidoreductase Polyunsaturated fatty acid biosynthesi |
| r0511 | steroyl-CoA,hydrogen-donor:oxygen oxidoreductase Polyunsaturated fatty acid biosynthesi |
| r0537 | Sphinganine-1-phosphate pamlmitaldehyde-lyase Sphingolipid metabolism EC:4.1.2.27 |
| r0546 | Phenylacetaldehyde:NAD+ oxidoreductase Phenylalanine metabolism / Styrene degradation E |
| r0548 | Aldehyde:NADP+ oxidoreductase Phenylalanine metabolism EC:1.2.1.5 |
| r0598 | L-Fucose ketol-isomerase Fructose and mannose metabolism EC:5.3.1.25 |
| r0625 | 3alpha,7alpha,12alpha-Trihydroxy-5beta-cholestan-26-al:NAD+ 26-oxidoreductase Bile acid |
| r0626 | 5beta-Cholestane-3alpha,7alpha,12alpha,26-tetraol:NAD+ 26-oxidoreductase Bile acid bios |
| r0648 | (5-Glutamyl)-peptide:amino-acid 5-glutamyltransferase Cyanoamino acid metabolism EC:2.3 |
| r0649 | (5-Glutamyl)-peptide:amino-acid 5-glutamyltransferase Cyanoamino acid metabolism EC:2.3 |
| r0673 | 6-Lactoyl-5,6,7,8-tetrahydropterin:NADP+ 2-oxidoreductase Folate biosynthesis EC:1.1.1. |
| r0678 | Acyl-[acyl-carrier-protein]:malonyl-[acyl-carrier-protein] C-acyltransferase (decarboxy |
| r0681 | (3R)-3-Hydroxybutanoyl-[acyl-carrier-protein] hydro-lyase Fatty acid biosynthesis EC:2. |
| r0682 | Butyryl-[acyl-carrier protein]:malonyl-CoA C-acyltransferase(decarboxylating, oxoacyl- |
| r0691 | (3R)-3-Hydroxybutanoyl-[acyl-carrier protein]:NADP+ oxidoreductase Fatty acid biosynthe |
| r0692 | (3R)-3-Hydroxydecanoyl-[acyl-carrier-protein]:NADP+ oxidoreductase Fatty acid biosynthe |

r0693 (3R)-3-Hydroxybutanoyl-[acyl-carrier-protein] hydro-lyase Fatty acid biosynthesis EC:2.3.1.16
r0694 (3R)-3-Hydroxyoctanoyl-[acyl-carrier-protein]:NADP+ oxidoreductase Fatty acid biosynthesis EC:2.3.1.17
r0695 (3R)-3-Hydroxybutanoyl-[acyl-carrier-protein] hydro-lyase; (3R)-3-Hydroxyoctanoyl-[acyl-carrier-protein] hydro-lyase
r0696 (3R)-3-Hydroxypalmitoyl-[acyl-carrier-protein]:NADP+ oxidoreductase Fatty acid biosynthesis EC:2.3.1.18
r0697 (3R)-3-Hydroxypalmitoyl-[acyl-carrier-protein] hydro-lyase Fatty acid biosynthesis EC:2.3.1.19
r0701 (3R)-3-Hydroxytetradecanoyl-[acyl-carrier-protein]:NADP+ oxidoreductase Fatty acid biosynthesis EC:2.3.1.20
r0702 (3R)-3-Hydroxypalmitoyl-[acyl-carrier-protein] hydro-lyase Fatty acid biosynthesis EC:2.3.1.21
r0708 2-Amino-4-hydroxy-6-(erythro-1,2,3-trihydroxypropyl) dihydropteridine triphosphate 7,8-dihydropteridine triphosphate 7,8-dihydropteridine triphosphate
r0709
r0712 Dodecanoyl-[acyl-carrier protein]: malonyl-CoA C-acyltransferase(decarboxylating, oxoacyl-acyltransferase)
r0713 dodecanoyl-[acyl-carrier-protein]:malonyl-[acyl-carrier-protein] C-acyltransferase (decarboxylating, oxoacyl-acyltransferase)
r0737 3-Ketolactose galactohydrolase Galactose metabolism EC:3.2.1.23
r0760 butyryl-[acyl-carrier protein]:malonyl-[acyl-carrier-protein] C-acyltransferase (decarboxylating, oxoacyl-acyltransferase)
r0761 (3R)-3-Hydroxyhexanoyl-[acyl-carrier-protein]:NADP+ oxidoreductase Fatty acid biosynthesis EC:2.3.1.22
r0762 (3R)-3-Hydroxybutanoyl-[acyl-carrier-protein] hydro-lyase Fatty acid biosynthesis EC:2.3.1.23
r0763 Hexanoyl-[acyl-carrier protein]:oxoacyl- and enoyl-reducing and thioester-hydrolysing
r0764 hexanoyl-[acyl-carrier protein]:malonyl-[acyl-carrier-protein] C-acyltransferase (decarboxylating, oxoacyl-acyltransferase)
r0765 Octanoyl-[acyl-carrier protein]:malonyl-CoA C-acyltransferase(decarboxylating, oxoacyl-acyltransferase)
r0766 Octanoyl-[acyl-carrier protein]:malonyl-[acyl-carrier-protein] C-acyltransferase (decarboxylating, oxoacyl-acyltransferase)
r0767 Decanoyl-[acyl-carrier protein]:malonyl-CoA C-acyltransferase(decarboxylating, oxoacyl-acyltransferase)
r0768 Decanoyl-[acyl-carrier protein]:malonyl-[acyl-carrier-protein] C-acyltransferase (decarboxylating, oxoacyl-acyltransferase)
r0769 (3R)-3-Hydroxydodecanoyl-[acyl-carrier-protein]:NADP+ oxidoreductase Fatty acid biosynthesis EC:2.3.1.24
r0770 (3R)-3-Hydroxybutanoyl-[acyl-carrier-protein] hydro-lyase Fatty acid biosynthesis EC:2.3.1.25
r0771 Tetradecanoyl-[acyl-carrier protein]:malonyl-CoA C-acyltransferase(decarboxylating, oxoacyl-acyltransferase)
r0772 Tetradecanoyl-[acyl-carrier protein]:malonyl-[acyl-carrier-protein] C-acyltransferase (decarboxylating, oxoacyl-acyltransferase)
r0773 Hexadecanoyl-[acyl-carrier protein]:malonyl-CoA C-acyltransferase(decarboxylating, oxoacyl-acyltransferase)
r0775 Formamidopyrimidine nucleoside triphosphate 7,8-8,9-dihydrolase Folate biosynthesis EC:3.5.4.16
r0776
r0777 GTP 7,8-8,9-dihydrolase Folate biosynthesis EC:3.5.4.16
r0778
r0786 sphinganine-1-phosphate palmitaldehyde-lyase Sphingolipid metabolism EC:4.1.2.27
r0800 Virtual reaction/potential definition
r0802 Vesicular transport
r0803 Vesicular transport
r0804 Vesicular transport
r0805 Vesicular transport
r0806 Vesicular transport
r0807 Vesicular transport
r0808 Vesicular transport
r0825 Vesicular transport
r0826 Transport reaction
r0859 Postulated transport reaction
r0886 Postulated transport reaction
r0925 Vesicular transport
r0927 Free diffusion
r0988 Postulated transport reaction
r0992 Na(+)/bile acid cotransporter Active transport
r1000 Facilitated diffusion
r1001 Facilitated diffusion
r1002 Facilitated diffusion
r1003 Facilitated diffusion
r1004 Facilitated diffusion
r1005 Facilitated diffusion
r1006 Facilitated diffusion
r1021 Postulated transport reaction
r1027 Active transport
r1033 Vesicular transport
r1034 Vesicular transport
r1048 Vesicular transport
r1049 Vesicular transport
r1054 Vesicular transport
r1055 Vesicular transport
r1056 Vesicular transport
r1057 Vesicular transport

r1059 Major Facilitator(MFS) TCDB:2.A.18.6.7
 r1061 Vesicular transport
 r1062 Vesicular transport
 r1063 Vesicular transport
 r1064 Postulated transport reaction
 r1067 Vesicular transport
 r1068 Vesicular transport
 r1071 Transport reaction
 r1073 Transport reaction
 r1074 Vesicular transport
 r1076 Postulated transport reaction
 r1077 Vesicular transport
 r1080 Vesicular transport
 r1081 Vesicular transport
 r1082 Vesicular transport
 r1092 albumin Protein assembly
 r1093 serpin peptidase inhibitor, clade A (alpha-1 antiproteinase, antitrypsin), member 3 Pr
 r1094 serpin peptidase inhibitor, clade A (alpha-1 antiproteinase, antitrypsin), member 1 Pr
 r1095 apolipoprotein B Protein assembly
 r1096 NADH dehydrogenase (ubiquinone) 1, alpha/beta subcomplex, 1 Protein assembly
 r1097 ACP Protein assembly
 r1098 Apo-CIB Protein assembly
 r1099 Apo-CII Protein assembly
 r1100 Apo-CIII Protein assembly
 r1101 Fibrinogen alpha chain Protein assembly
 r1102 Haptoglobin Protein assembly
 r1103 Plasminogen Protein assembly
 r1104 Prothrombin Protein assembly
 r1105 T9 Protein assembly
 r1112 Apo-E Protein assembly
 r1113 Apo-AI Protein assembly
 r1127 Transport reaction
 r1128 Transport reaction
 r1129 Transport reaction
 r1130 Transport reaction
 r1131 Transport reaction
 r1132 Transport reaction
 r1133 Transport reaction
 r1134 methylsterol monooxygenase Biosynthesis of steroids EC:1.14.13.72
 r1135 hydroxysteroid (17-beta) dehydrogenase 7 Biosynthesis of steroids EC:1.1.1.270
 r1136 sterol-4alpha-carboxylate 3-dehydrogenase (decarboxylating) Biosynthesis of steroids EC
 r1137 NAD(P) dependent steroid dehydrogenase-like EC:1.1.1.170
 r1140 Vesicular transport
 r1146 Biosynthesis of steroids Enzyme catalyzed
 r1159 Vesicular transport
 r1165 EC:2.3.1.26
 r1166 EC:2.3.1.26
 r1169 EC:2.3.1.26
 r1170 EC:2.3.1.26
 r1171 EC:2.3.1.26
 r1173 EC:3.1.1.13
 r1174 EC:3.1.1.13
 r1175 EC:3.1.1.13
 r1176 EC:3.1.1.13
 r1178 EC:3.1.1.13
 r1180 EC:3.1.1.13
 r1181 EC:3.1.1.13
 r1182 EC:3.1.1.13
 r1183 EC:3.1.1.13
 r1184 EC:3.1.1.13
 r1185 EC:2.3.1.15
 r1186 EC:2.3.1.15
 r1187 EC:2.3.1.15
 r1188 EC:2.3.1.15

| | |
|-------|---|
| r1189 | EC:2.3.1.15 |
| r1190 | EC:2.3.1.15 |
| r1251 | EC:6.2.1.3 |
| r1253 | EC:6.2.1.3 |
| r1290 | Postulated transport reaction |
| r1293 | ADF Protein assembly |
| r1294 | MTRX Protein assembly |
| r1313 | 3-oxoacyl-ACP synthase, mitochondrial Polyunsaturated fatty acid biosynthesis EC:2.3.1.85 |
| r1314 | fatty acid synthase Polyunsaturated fatty acid biosynthesis EC:2.3.1.85 |
| r1315 | fatty acid synthase Polyunsaturated fatty acid biosynthesis EC:2.3.1.85 |
| r1316 | fatty acid synthase Polyunsaturated fatty acid biosynthesis EC:2.3.1.85 |
| r1317 | oleoyl-ACP hydrolase EC:2.3.1.85 |
| r1319 | Virtual reaction/potential definition |
| r1320 | Virtual reaction/potential definition |
| r1321 | Virtual reaction/potential definition |
| r1322 | Virtual reaction/potential definition |
| r1323 | Virtual reaction/potential definition |
| r1324 | Virtual reaction/potential definition |
| r1325 | Virtual reaction/potential definition |
| r1326 | Virtual reaction/potential definition |
| r1327 | Virtual reaction/potential definition |
| r1328 | Virtual reaction/potential definition |
| r1329 | Virtual reaction/potential definition |
| r1330 | Virtual reaction/potential definition |
| r1331 | Virtual reaction/potential definition |
| r1332 | Virtual reaction/potential definition |
| r1333 | Protein degradation |
| r1334 | Protein degradation |
| r1335 | Protein degradation |
| r1336 | Protein degradation |
| r1337 | Protein degradation |
| r1338 | Protein degradation |
| r1339 | Protein degradation |
| r1340 | Protein degradation |
| r1341 | Protein degradation |
| r1342 | Protein degradation |
| r1343 | Protein degradation |
| r1344 | Protein degradation |
| r1345 | Protein degradation |
| r1346 | Protein degradation |
| r1347 | Protein degradation |
| r1348 | Protein degradation |
| r1349 | Protein degradation |
| r1350 | Protein degradation |
| r1351 | Protein degradation |
| r1352 | Protein degradation |
| r1353 | Protein degradation |
| r1354 | Protein degradation |
| r1355 | Protein degradation |
| r1356 | Protein degradation |
| r1357 | Protein degradation |
| r1358 | Protein degradation |
| r1359 | Protein degradation |
| r1382 | folylpolyglutamyl synthetase EC:6.3.2.17 |
| r1383 | gamma-glutamyl hydrolase EC:3.4.19.9 |
| r1386 | Virtual reaction/potential definition |
| r1391 | amylase-1,6-glucosidase, 4-alpha-glucanotransferase EC:2.4.1.25 |
| r1392 | amylase-1,6-glucosidase, 4-alpha-glucanotransferase EC:3.2.1.33 |
| r1393 | EC:2.4.1.1 |
| r1394 | EC:2.3.1.21 |
| r1395 | carnitine acetyltransferase EC:2.3.1.7 |
| r1398 | EC:2.3.1.21 |
| r1399 | carnitine acetyltransferase EC:2.3.1.7 |
| r1402 | glycogenin Protein assembly |

r1403 Protein degradation
 r1411 D-Galactosyl-N-acetyl-D-galactosaminyl-(N-acetylneuraminyl)-D- galactosyl-D-glucosylcer
 r1430 [Acyl-carrier-protein] 4-pantetheine-phosphohydrolase Pantothenate and CoA biosynthesis
 r1431 2-Deoxyuridine 5-diphosphate:oxidized-thioredoxin 2-oxidoreductase Pyrimidine metabolis
 r1432 2-Deoxyuridine 5-diphosphate:oxidized-thioredoxin 2-oxidoreductase Pyrimidine metabolis
 r1436 Transport reaction
 r1437 Transport reaction
 r1440 Transport reaction
 r1441 Active transport
 r1455 Transport reaction
 r1457 hexadecanal:NADP+ delta2-oxidoreductase EC:1.3.1.27
 r1468 Postulated transport reaction
 r1472 long-chain-acyl-CoA dehydrogenase EC:1.3.99.13
 r1474 EC:4.2.1.17
 r1477 EC:1.1.1.35
 r1479 EC:2.3.1.16
 r1481 EC:2.3.1.16
 r1501 Glycoside-Pentoside-Hexuronide (GPH):Cation Symporter TCDB:2.A.28.1.1
 r1502 Glycoside-Pentoside-Hexuronide (GPH):Cation Symporter TCDB:2.A.28.1.1
 r1503 Glycoside-Pentoside-Hexuronide (GPH):Cation Symporter TCDB:2.A.28.1.1
 r1526 ATP-binding Cassette (ABC) TCDB:3.A.1.211.1
 r1531 ATP-binding Cassette (ABC) TCDB:3.A.1.208.15
 r1532 ATP-binding Cassette (ABC) TCDB:3.A.1.208.15
 r1533 ATP-binding Cassette (ABC) TCDB:3.A.1.208.15
 r2073 Zinc (Zn2+)-Iron (Fe2+) Permease (ZIP), TCDB:2.A.55.2.3
 r2143 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2146 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2147 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2148 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2149 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2151 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2152 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2153 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2154 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2155 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2156 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2157 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2158 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2159 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2160 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2161 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2162 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2163 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2164 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2165 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2166 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2167 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2168 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2169 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2170 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2171 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2172 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2173 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2174 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2175 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2176 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2177 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2178 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2179 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2180 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2181 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2182 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2183 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14
 r2184 Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14

[illegible]

[illegible]

| | |
|-----------|--|
| r2495 | Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14 |
| r2496 | Resistance-Nodulation-Cell Division (RND) TCDB:2.A.60.1.14 |
| r2498 | ATP-binding Cassette (ABC) TCDB:3.A.1.203.3 |
| r2502 | ATP-binding Cassette (ABC) TCDB:3.A.1.203.3 |
| EX_so3(e) | Sulfite exchange |
| RE0066C | RE0066 |
| RE0066M | RE0066 |
| RE0066R | RE0066 |
| RE0124C | RE0124 |
| RE0344M | RE0344 |
| RE0344X | RE0344 |
| RE0452N | RE0452 |
| RE0456M | RE0456 |
| RE0456N | RE0456 |
| RE0512C | RE0512 |
| RE0512X | RE0512 |
| RE0549C | RE0549 |
| RE0569C | RE0569 |
| RE0570C | RE0570 |
| RE0571C | RE0571 |
| RE0572N | RE0572 |
| RE0573N | RE0573 |
| RE0574C | RE0574 |
| RE0575C | RE0575 |
| RE0576C | RE0576 |
| RE0577M | RE0577 |
| RE0577X | RE0577 |
| RE0578C | RE0578 |
| RE0578M | RE0578 |
| RE0578X | RE0578 |
| RE0579C | RE0579 |
| RE0579M | RE0579 |
| RE0579X | RE0579 |
| RE0580L | RE0580 |
| RE0580R | RE0580 |
| RE0581C | RE0581 |
| RE0581R | RE0581 |
| RE0582N | RE0582 |
| RE0583N | RE0583 |
| RE0688C | RE0688 |
| RE0688X | RE0688 |
| RE0689C | RE0689 |
| RE0689X | RE0689 |
| RE0690C | RE0690 |
| RE0690X | RE0690 |
| RE0702C | RE0702 |
| RE0702L | RE0702 |
| RE0702M | RE0702 |
| RE0702N | RE0702 |
| RE0827C | RE0827 |
| RE0827X | RE0827 |
| RE0828C | RE0828 |
| RE0828X | RE0828 |
| RE0864C | RE0864 |
| RE0875C | RE0875 |
| RE0908G | RE0908 |
| RE0908R | RE0908 |
| RE0915C | RE0915 |
| RE0916C | RE0916 |
| RE0916G | RE0916 |
| RE0916R | RE0916 |
| RE0918C | RE0918 |
| RE0918G | RE0918 |
| RE0918R | RE0918 |

| | |
|---------|--------|
| RE0919C | RE0919 |
| RE0919R | RE0919 |
| RE0920C | RE0920 |
| RE0920R | RE0920 |
| RE0921C | RE0921 |
| RE0921R | RE0921 |
| RE0922C | RE0922 |
| RE0922R | RE0922 |
| RE0923C | RE0923 |
| RE0923R | RE0923 |
| RE0924C | RE0924 |
| RE0924R | RE0924 |
| RE0925C | RE0925 |
| RE0925R | RE0925 |
| RE0926C | RE0926 |
| RE0927C | RE0927 |
| RE0927R | RE0927 |
| RE0928C | RE0928 |
| RE0928R | RE0928 |
| RE0935C | RE0935 |
| RE0936C | RE0936 |
| RE0937C | RE0937 |
| RE0938C | RE0938 |
| RE0944C | RE0944 |
| RE0958C | RE0958 |
| RE1050C | RE1050 |
| RE1050E | RE1050 |
| RE1050L | RE1050 |
| RE1050N | RE1050 |
| RE1062C | RE1062 |
| RE1062M | RE1062 |
| RE1063C | RE1063 |
| RE1064C | RE1064 |
| RE1077C | RE1077 |
| RE1096C | RE1096 |
| RE1096M | RE1096 |
| RE1096R | RE1096 |
| RE1099C | RE1099 |
| RE1099G | RE1099 |
| RE1099L | RE1099 |
| RE1099R | RE1099 |
| RE1100G | RE1100 |
| RE1100L | RE1100 |
| RE1100R | RE1100 |
| RE1134C | RE1134 |
| RE1134M | RE1134 |
| RE1134R | RE1134 |
| RE1135G | RE1135 |
| RE1135L | RE1135 |
| RE1135R | RE1135 |
| RE1233M | RE1233 |
| RE1234C | RE1234 |
| RE1235C | RE1235 |
| RE1236C | RE1236 |
| RE1238X | RE1238 |
| RE1240C | RE1240 |
| RE1266C | RE1266 |
| RE1308C | RE1308 |
| RE1308M | RE1308 |
| RE1309C | RE1309 |
| RE1309M | RE1309 |
| RE1310C | RE1310 |
| RE1310M | RE1310 |
| RE1311C | RE1311 |

| | |
|---------|--------|
| RE1311M | RE1311 |
| RE1317C | RE1317 |
| RE1441G | RE1441 |
| RE1473C | RE1473 |
| RE1508C | RE1508 |
| RE1514M | RE1514 |
| RE1514X | RE1514 |
| RE1516X | RE1516 |
| RE1517X | RE1517 |
| RE1518X | RE1518 |
| RE1519X | RE1519 |
| RE1520X | RE1520 |
| RE1521X | RE1521 |
| RE1522X | RE1522 |
| RE1523X | RE1523 |
| RE1525C | RE1525 |
| RE1525X | RE1525 |
| RE1526C | RE1526 |
| RE1526X | RE1526 |
| RE1527C | RE1527 |
| RE1527X | RE1527 |
| RE1531X | RE1531 |
| RE1532X | RE1532 |
| RE1533X | RE1533 |
| RE1534X | RE1534 |
| RE1537C | RE1537 |
| RE1537X | RE1537 |
| RE1538C | RE1538 |
| RE1538X | RE1538 |
| RE1539C | RE1539 |
| RE1539X | RE1539 |
| RE1573X | RE1573 |
| RE1582C | RE1582 |
| RE1582L | RE1582 |
| RE1582R | RE1582 |
| RE1587C | RE1587 |
| RE1587L | RE1587 |
| RE1587R | RE1587 |
| RE1627C | RE1627 |
| RE1628C | RE1628 |
| RE1629C | RE1629 |
| RE1630C | RE1630 |
| RE1630R | RE1630 |
| RE1631C | RE1631 |
| RE1632C | RE1632 |
| RE1632R | RE1632 |
| RE1635C | RE1635 |
| RE1635M | RE1635 |
| RE1635R | RE1635 |
| RE1635X | RE1635 |
| RE1651C | RE1651 |
| RE1653C | RE1653 |
| RE1699C | RE1699 |
| RE1700C | RE1700 |
| RE1701C | RE1701 |
| RE1702C | RE1702 |
| RE1711C | RE1711 |
| RE1711M | RE1711 |
| RE1796C | RE1796 |
| RE1803C | RE1803 |
| RE1806C | RE1806 |
| RE1806R | RE1806 |
| RE1808R | RE1808 |
| RE1809C | RE1809 |

| | |
|---------|--------|
| RE1809R | RE1809 |
| RE1811C | RE1811 |
| RE1811R | RE1811 |
| RE1812C | RE1812 |
| RE1812R | RE1812 |
| RE1815C | RE1815 |
| RE1815M | RE1815 |
| RE1815R | RE1815 |
| RE1815X | RE1815 |
| RE1816C | RE1816 |
| RE1816M | RE1816 |
| RE1816R | RE1816 |
| RE1816X | RE1816 |
| RE1817C | RE1817 |
| RE1817M | RE1817 |
| RE1817R | RE1817 |
| RE1817X | RE1817 |
| RE1818C | RE1818 |
| RE1818M | RE1818 |
| RE1818R | RE1818 |
| RE1818X | RE1818 |
| RE1819C | RE1819 |
| RE1819M | RE1819 |
| RE1819X | RE1819 |
| RE1826M | RE1826 |
| RE1827C | RE1827 |
| RE1827M | RE1827 |
| RE1828C | RE1828 |
| RE1828M | RE1828 |
| RE1829C | RE1829 |
| RE1829M | RE1829 |
| RE1830C | RE1830 |
| RE1830M | RE1830 |
| RE1834M | RE1834 |
| RE1834X | RE1834 |
| RE1835M | RE1835 |
| RE1835X | RE1835 |
| RE1836C | RE1836 |
| RE1836M | RE1836 |
| RE1846C | RE1846 |
| RE1846X | RE1846 |
| RE1860C | RE1860 |
| RE1899C | RE1899 |
| RE1904C | RE1904 |
| RE1904R | RE1904 |
| RE1905C | RE1905 |
| RE1905R | RE1905 |
| RE1906C | RE1906 |
| RE1906R | RE1906 |
| RE1907C | RE1907 |
| RE1915C | RE1915 |
| RE1916C | RE1916 |
| RE1916X | RE1916 |
| RE1917C | RE1917 |
| RE1918C | RE1918 |
| RE1919C | RE1919 |
| RE1920C | RE1920 |
| RE1921C | RE1921 |
| RE1922C | RE1922 |
| RE1923C | RE1923 |
| RE1925C | RE1925 |
| RE1927C | RE1927 |
| RE1933C | RE1933 |
| RE1938C | RE1938 |

| | |
|---------|--------|
| RE1938R | RE1938 |
| RE1941C | RE1941 |
| RE1941R | RE1941 |
| RE1942C | RE1942 |
| RE1942R | RE1942 |
| RE1943C | RE1943 |
| RE1943R | RE1943 |
| RE1944C | RE1944 |
| RE1952C | RE1952 |
| RE1952R | RE1952 |
| RE1952X | RE1952 |
| RE1954C | RE1954 |
| RE1956C | RE1956 |
| RE1956R | RE1956 |
| RE1956X | RE1956 |
| RE1957G | RE1957 |
| RE1978C | RE1978 |
| RE2026C | RE2026 |
| RE2027C | RE2027 |
| RE2028C | RE2028 |
| RE2029C | RE2029 |
| RE2030M | RE2030 |
| RE2031M | RE2031 |
| RE2032M | RE2032 |
| RE2034C | RE2034 |
| RE2040C | RE2040 |
| RE2041C | RE2041 |
| RE2048N | RE2048 |
| RE2048R | RE2048 |
| RE2049C | RE2049 |
| RE2050C | RE2050 |
| RE2050R | RE2050 |
| RE2051C | RE2051 |
| RE2051G | RE2051 |
| RE2051R | RE2051 |
| RE2067C | RE2067 |
| RE2068C | RE2068 |
| RE2070C | RE2070 |
| RE2078M | RE2078 |
| RE2080C | RE2080 |
| RE2081C | RE2081 |
| RE2111M | RE2111 |
| RE2112C | RE2112 |
| RE2112R | RE2112 |
| RE2117M | RE2117 |
| RE2122C | RE2122 |
| RE2124C | RE2124 |
| RE2127C | RE2127 |
| RE2128C | RE2128 |
| RE2129C | RE2129 |
| RE2130C | RE2130 |
| RE2131C | RE2131 |
| RE2132C | RE2132 |
| RE2133C | RE2133 |
| RE2138C | RE2138 |
| RE2139C | RE2139 |
| RE2140C | RE2140 |
| RE2141C | RE2141 |
| RE2146C | RE2146 |
| RE2146R | RE2146 |
| RE2147R | RE2147 |
| RE2149C | RE2149 |
| RE2149R | RE2149 |
| RE2150C | RE2150 |

| | |
|---------|--------|
| RE2150R | RE2150 |
| RE2151C | RE2151 |
| RE2151R | RE2151 |
| RE2152C | RE2152 |
| RE2154C | RE2154 |
| RE2155C | RE2155 |
| RE2155R | RE2155 |
| RE2156M | RE2156 |
| RE2202C | RE2202 |
| RE2203C | RE2203 |
| RE2220C | RE2220 |
| RE2221C | RE2221 |
| RE2221M | RE2221 |
| RE2223M | RE2223 |
| RE2235C | RE2235 |
| RE2235R | RE2235 |
| RE2248C | RE2248 |
| RE2249C | RE2249 |
| RE2250C | RE2250 |
| RE2251C | RE2251 |
| RE2252C | RE2252 |
| RE2265C | RE2265 |
| RE2269C | RE2269 |
| RE2270C | RE2270 |
| RE2272C | RE2272 |
| RE2272L | RE2272 |
| RE2273C | RE2273 |
| RE2292C | RE2292 |
| RE2296C | RE2296 |
| RE2296X | RE2296 |
| RE2306C | RE2306 |
| RE2318C | RE2318 |
| RE2318M | RE2318 |
| RE2318R | RE2318 |
| RE2318X | RE2318 |
| RE2319C | RE2319 |
| RE2319M | RE2319 |
| RE2319R | RE2319 |
| RE2319X | RE2319 |
| RE2327C | RE2327 |
| RE2333C | RE2333 |
| RE2334C | RE2334 |
| RE2335C | RE2335 |
| RE2346C | RE2346 |
| RE2349M | RE2349 |
| RE2360C | RE2360 |
| RE2360N | RE2360 |
| RE2373C | RE2373 |
| RE2375C | RE2375 |
| RE2377C | RE2377 |
| RE2382C | RE2382 |
| RE2382R | RE2382 |
| RE2383C | RE2383 |
| RE2383R | RE2383 |
| RE2384C | RE2384 |
| RE2386C | RE2386 |
| RE2387C | RE2387 |
| RE2387R | RE2387 |
| RE2398C | RE2398 |
| RE2398R | RE2398 |
| RE2404R | RE2404 |
| RE2405R | RE2405 |
| RE2407C | RE2407 |
| RE2410C | RE2410 |

| | |
|---------|--------|
| RE2410N | RE2410 |
| RE2427M | RE2427 |
| RE2428M | RE2428 |
| RE2429M | RE2429 |
| RE2439C | RE2439 |
| RE2440C | RE2440 |
| RE2442C | RE2442 |
| RE2443C | RE2443 |
| RE2443M | RE2443 |
| RE2444C | RE2444 |
| RE2445C | RE2445 |
| RE2452C | RE2452 |
| RE2453M | RE2453 |
| RE2454M | RE2454 |
| RE2459C | RE2459 |
| RE2474C | RE2474 |
| RE2474R | RE2474 |
| RE2476C | RE2476 |
| RE2477C | RE2477 |
| RE2493C | RE2493 |
| RE2513C | RE2513 |
| RE2513L | RE2513 |
| RE2513N | RE2513 |
| RE2514C | RE2514 |
| RE2514L | RE2514 |
| RE2514N | RE2514 |
| RE2520C | RE2520 |
| RE2521C | RE2521 |
| RE2522C | RE2522 |
| RE2522X | RE2522 |
| RE2523C | RE2523 |
| RE2523X | RE2523 |
| RE2524C | RE2524 |
| RE2524X | RE2524 |
| RE2525C | RE2525 |
| RE2525X | RE2525 |
| RE2526C | RE2526 |
| RE2533C | RE2533 |
| RE2541L | RE2541 |
| RE2562C | RE2562 |
| RE2563C | RE2563 |
| RE2591C | RE2591 |
| RE2594C | RE2594 |
| RE2596C | RE2596 |
| RE2601C | RE2601 |
| RE2605C | RE2605 |
| RE2622C | RE2622 |
| RE2622R | RE2622 |
| RE2624M | RE2624 |
| RE2624X | RE2624 |
| RE2632C | RE2632 |
| RE2632M | RE2632 |
| RE2633C | RE2633 |
| RE2633R | RE2633 |
| RE2635C | RE2635 |
| RE2635R | RE2635 |
| RE2636C | RE2636 |
| RE2636R | RE2636 |
| RE2637C | RE2637 |
| RE2637X | RE2637 |
| RE2638C | RE2638 |
| RE2638X | RE2638 |
| RE2640C | RE2640 |
| RE2642C | RE2642 |

| | |
|---------|--------|
| RE2644C | RE2644 |
| RE2649X | RE2649 |
| RE2658C | RE2658 |
| RE2677N | RE2677 |
| RE2677R | RE2677 |
| RE2680C | RE2680 |
| RE2680G | RE2680 |
| RE2704C | RE2704 |
| RE2705C | RE2705 |
| RE2717L | RE2717 |
| RE2718C | RE2718 |
| RE2718G | RE2718 |
| RE2722C | RE2722 |
| RE2722G | RE2722 |
| RE2746C | RE2746 |
| RE2766C | RE2766 |
| RE2768C | RE2768 |
| RE2768M | RE2768 |
| RE2768R | RE2768 |
| RE2782C | RE2782 |
| RE2813C | RE2813 |
| RE2848C | RE2848 |
| RE2849C | RE2849 |
| RE2850C | RE2850 |
| RE2851C | RE2851 |
| RE2852C | RE2852 |
| RE2853C | RE2853 |
| RE2854C | RE2854 |
| RE2856C | RE2856 |
| RE2857C | RE2857 |
| RE2858C | RE2858 |
| RE2859C | RE2859 |
| RE2860C | RE2860 |
| RE2861C | RE2861 |
| RE2862C | RE2862 |
| RE2863C | RE2863 |
| RE2864C | RE2864 |
| RE2865C | RE2865 |
| RE2866C | RE2866 |
| RE2867C | RE2867 |
| RE2868C | RE2868 |
| RE2869C | RE2869 |
| RE2870C | RE2870 |
| RE2871C | RE2871 |
| RE2872C | RE2872 |
| RE2873C | RE2873 |
| RE2874C | RE2874 |
| RE2875C | RE2875 |
| RE2876C | RE2876 |
| RE2877C | RE2877 |
| RE2878C | RE2878 |
| RE2880C | RE2880 |
| RE2888C | RE2888 |
| RE2888N | RE2888 |
| RE2897C | RE2897 |
| RE2898C | RE2898 |
| RE2899C | RE2899 |
| RE2908C | RE2908 |
| RE2908M | RE2908 |
| RE2908X | RE2908 |
| RE2909C | RE2909 |
| RE2909M | RE2909 |
| RE2909X | RE2909 |
| RE2910C | RE2910 |

| | |
|---------|--------|
| RE2910M | RE2910 |
| RE2910X | RE2910 |
| RE2911C | RE2911 |
| RE2912M | RE2912 |
| RE2912X | RE2912 |
| RE2913M | RE2913 |
| RE2913X | RE2913 |
| RE2914M | RE2914 |
| RE2914X | RE2914 |
| RE2915M | RE2915 |
| RE2915X | RE2915 |
| RE2916M | RE2916 |
| RE2916X | RE2916 |
| RE2917M | RE2917 |
| RE2917X | RE2917 |
| RE2919M | RE2919 |
| RE2919X | RE2919 |
| RE2920M | RE2920 |
| RE2920X | RE2920 |
| RE2921M | RE2921 |
| RE2921X | RE2921 |
| RE2948C | RE2948 |
| RE2958C | RE2958 |
| RE2972G | RE2972 |
| RE2972R | RE2972 |
| RE2973G | RE2973 |
| RE2974G | RE2974 |
| RE2975C | RE2975 |
| RE2975M | RE2975 |
| RE2977C | RE2977 |
| RE2985M | RE2985 |
| RE2989X | RE2989 |
| RE2990X | RE2990 |
| RE2991X | RE2991 |
| RE2992M | RE2992 |
| RE2992X | RE2992 |
| RE2993X | RE2993 |
| RE2994X | RE2994 |
| RE2995M | RE2995 |
| RE2995X | RE2995 |
| RE2997X | RE2997 |
| RE3010C | RE3010 |
| RE3010M | RE3010 |
| RE3010R | RE3010 |
| RE3010X | RE3010 |
| RE3011M | RE3011 |
| RE3012C | RE3012 |
| RE3012M | RE3012 |
| RE3013C | RE3013 |
| RE3013R | RE3013 |
| RE3014C | RE3014 |
| RE3015C | RE3015 |
| RE3018C | RE3018 |
| RE3018R | RE3018 |
| RE3019C | RE3019 |
| RE3019R | RE3019 |
| RE3020C | RE3020 |
| RE3020R | RE3020 |
| RE3021C | RE3021 |
| RE3022C | RE3022 |
| RE3033C | RE3033 |
| RE3033N | RE3033 |
| RE3033R | RE3033 |
| RE3036C | RE3036 |

| | |
|---------|--------|
| RE3036N | RE3036 |
| RE3038C | RE3038 |
| RE3038N | RE3038 |
| RE3038R | RE3038 |
| RE3038X | RE3038 |
| RE3039C | RE3039 |
| RE3040C | RE3040 |
| RE3040R | RE3040 |
| RE3040X | RE3040 |
| RE3041C | RE3041 |
| RE3041N | RE3041 |
| RE3044C | RE3044 |
| RE3044N | RE3044 |
| RE3045C | RE3045 |
| RE3051C | RE3051 |
| RE3052C | RE3052 |
| RE3053C | RE3053 |
| RE3066X | RE3066 |
| RE3072X | RE3072 |
| RE3073X | RE3073 |
| RE3075C | RE3075 |
| RE3075X | RE3075 |
| RE3076X | RE3076 |
| RE3079C | RE3079 |
| RE3081X | RE3081 |
| RE3082X | RE3082 |
| RE3083X | RE3083 |
| RE3084X | RE3084 |
| RE3086X | RE3086 |
| RE3087X | RE3087 |
| RE3088X | RE3088 |
| RE3089X | RE3089 |
| RE3090X | RE3090 |
| RE3092X | RE3092 |
| RE3093X | RE3093 |
| RE3095C | RE3095 |
| RE3095L | RE3095 |
| RE3095X | RE3095 |
| RE3097X | RE3097 |
| RE3103C | RE3103 |
| RE3103R | RE3103 |
| RE3104C | RE3104 |
| RE3104R | RE3104 |
| RE3106C | RE3106 |
| RE3106R | RE3106 |
| RE3108C | RE3108 |
| RE3110C | RE3110 |
| RE3110R | RE3110 |
| RE3111C | RE3111 |
| RE3111M | RE3111 |
| RE3111R | RE3111 |
| RE3112C | RE3112 |
| RE3112R | RE3112 |
| RE3113C | RE3113 |
| RE3113R | RE3113 |
| RE3114R | RE3114 |
| RE3119C | RE3119 |
| RE3119R | RE3119 |
| RE3120C | RE3120 |
| RE3120R | RE3120 |
| RE3121C | RE3121 |
| RE3121R | RE3121 |
| RE3122C | RE3122 |
| RE3122R | RE3122 |

| | |
|---------|--------|
| RE3123C | RE3123 |
| RE3123R | RE3123 |
| RE3124C | RE3124 |
| RE3124R | RE3124 |
| RE3125C | RE3125 |
| RE3125R | RE3125 |
| RE3126C | RE3126 |
| RE3126R | RE3126 |
| RE3129N | RE3129 |
| RE3132C | RE3132 |
| RE3132R | RE3132 |
| RE3134C | RE3134 |
| RE3134R | RE3134 |
| RE3136C | RE3136 |
| RE3139X | RE3139 |
| RE3140X | RE3140 |
| RE3141X | RE3141 |
| RE3144C | RE3144 |
| RE3144M | RE3144 |
| RE3145X | RE3145 |
| RE3146C | RE3146 |
| RE3146R | RE3146 |
| RE3147C | RE3147 |
| RE3147R | RE3147 |
| RE3148C | RE3148 |
| RE3148R | RE3148 |
| RE3150C | RE3150 |
| RE3150R | RE3150 |
| RE3151C | RE3151 |
| RE3151R | RE3151 |
| RE3152C | RE3152 |
| RE3152R | RE3152 |
| RE3153C | RE3153 |
| RE3153R | RE3153 |
| RE3154C | RE3154 |
| RE3154R | RE3154 |
| RE3155C | RE3155 |
| RE3155R | RE3155 |
| RE3156X | RE3156 |
| RE3157X | RE3157 |
| RE3158X | RE3158 |
| RE3159X | RE3159 |
| RE3160C | RE3160 |
| RE3160R | RE3160 |
| RE3161C | RE3161 |
| RE3161R | RE3161 |
| RE3162C | RE3162 |
| RE3162R | RE3162 |
| RE3163C | RE3163 |
| RE3163R | RE3163 |
| RE3164C | RE3164 |
| RE3164R | RE3164 |
| RE3165C | RE3165 |
| RE3165R | RE3165 |
| RE3166C | RE3166 |
| RE3166R | RE3166 |
| RE3167C | RE3167 |
| RE3167R | RE3167 |
| RE3168C | RE3168 |
| RE3168R | RE3168 |
| RE3169C | RE3169 |
| RE3169R | RE3169 |
| RE3170C | RE3170 |
| RE3170R | RE3170 |

| | |
|---------|--------|
| RE3171C | RE3171 |
| RE3171R | RE3171 |
| RE3172C | RE3172 |
| RE3172R | RE3172 |
| RE3173C | RE3173 |
| RE3173R | RE3173 |
| RE3174C | RE3174 |
| RE3174R | RE3174 |
| RE3175C | RE3175 |
| RE3175R | RE3175 |
| RE3176C | RE3176 |
| RE3176R | RE3176 |
| RE3177M | RE3177 |
| RE3178M | RE3178 |
| RE3179M | RE3179 |
| RE3180C | RE3180 |
| RE3181C | RE3181 |
| RE3184M | RE3184 |
| RE3185M | RE3185 |
| RE3186M | RE3186 |
| RE3189M | RE3189 |
| RE3190M | RE3190 |
| RE3191M | RE3191 |
| RE3192M | RE3192 |
| RE3193M | RE3193 |
| RE3194M | RE3194 |
| RE3195M | RE3195 |
| RE3201C | RE3201 |
| RE3218L | RE3218 |
| RE3218R | RE3218 |
| RE3220C | RE3220 |
| RE3220L | RE3220 |
| RE3220R | RE3220 |
| RE3224C | RE3224 |
| RE3224R | RE3224 |
| RE3225C | RE3225 |
| RE3225R | RE3225 |
| RE3226C | RE3226 |
| RE3226R | RE3226 |
| RE3227C | RE3227 |
| RE3227R | RE3227 |
| RE3228C | RE3228 |
| RE3228R | RE3228 |
| RE3229C | RE3229 |
| RE3229R | RE3229 |
| RE3230C | RE3230 |
| RE3230R | RE3230 |
| RE3231C | RE3231 |
| RE3231R | RE3231 |
| RE3232C | RE3232 |
| RE3232R | RE3232 |
| RE3233C | RE3233 |
| RE3233G | RE3233 |
| RE3233L | RE3233 |
| RE3234C | RE3234 |
| RE3234R | RE3234 |
| RE3235C | RE3235 |
| RE3235R | RE3235 |
| RE3236C | RE3236 |
| RE3236R | RE3236 |
| RE3237C | RE3237 |
| RE3238C | RE3238 |
| RE3239C | RE3239 |
| RE3247M | RE3247 |

| | |
|---------|--------|
| RE3247X | RE3247 |
| RE3248M | RE3248 |
| RE3248X | RE3248 |
| RE3250C | RE3250 |
| RE3250M | RE3250 |
| RE3250X | RE3250 |
| RE3251M | RE3251 |
| RE3258C | RE3258 |
| RE3258R | RE3258 |
| RE3259C | RE3259 |
| RE3259R | RE3259 |
| RE3260C | RE3260 |
| RE3260R | RE3260 |
| RE3261C | RE3261 |
| RE3261R | RE3261 |
| RE3263C | RE3263 |
| RE3264C | RE3264 |
| RE3264R | RE3264 |
| RE3265C | RE3265 |
| RE3265R | RE3265 |
| RE3267E | RE3267 |
| RE3267G | RE3267 |
| RE3267M | RE3267 |
| RE3267N | RE3267 |
| RE3267R | RE3267 |
| RE3268C | RE3268 |
| RE3273G | RE3273 |
| RE3273R | RE3273 |
| RE3286C | RE3286 |
| RE3286R | RE3286 |
| RE3287C | RE3287 |
| RE3287R | RE3287 |
| RE3288C | RE3288 |
| RE3288R | RE3288 |
| RE3289C | RE3289 |
| RE3289R | RE3289 |
| RE3295C | RE3295 |
| RE3301G | RE3301 |
| RE3301R | RE3301 |
| RE3307C | RE3307 |
| RE3307M | RE3307 |
| RE3307X | RE3307 |
| RE3308C | RE3308 |
| RE3308M | RE3308 |
| RE3308R | RE3308 |
| RE3308X | RE3308 |
| RE3310C | RE3310 |
| RE3310R | RE3310 |
| RE3334M | RE3334 |
| RE3334X | RE3334 |
| RE3335C | RE3335 |
| RE3335M | RE3335 |
| RE3335R | RE3335 |
| RE3335X | RE3335 |
| RE3336M | RE3336 |
| RE3336X | RE3336 |
| RE3337M | RE3337 |
| RE3337X | RE3337 |
| RE3338C | RE3338 |
| RE3338M | RE3338 |
| RE3338X | RE3338 |
| RE3339C | RE3339 |
| RE3339M | RE3339 |
| RE3339X | RE3339 |

| | |
|---------|--------|
| RE3340C | RE3340 |
| RE3340M | RE3340 |
| RE3340X | RE3340 |
| RE3341M | RE3341 |
| RE3341X | RE3341 |
| RE3342M | RE3342 |
| RE3342X | RE3342 |
| RE3343C | RE3343 |
| RE3343M | RE3343 |
| RE3343X | RE3343 |
| RE3344M | RE3344 |
| RE3344X | RE3344 |
| RE3345C | RE3345 |
| RE3345M | RE3345 |
| RE3345R | RE3345 |
| RE3345X | RE3345 |
| RE3346R | RE3346 |
| RE3352C | RE3352 |
| RE3367C | RE3367 |
| RE3367X | RE3367 |
| RE3370C | RE3370 |
| RE3370R | RE3370 |
| RE3372C | RE3372 |
| RE3378C | RE3378 |
| RE3381L | RE3381 |
| RE3383M | RE3383 |
| RE3384M | RE3384 |
| RE3385M | RE3385 |
| RE3386M | RE3386 |
| RE3387M | RE3387 |
| RE3388M | RE3388 |
| RE3389M | RE3389 |
| RE3390M | RE3390 |
| RE3391M | RE3391 |
| RE3392M | RE3392 |
| RE3393M | RE3393 |
| RE3394M | RE3394 |
| RE3395M | RE3395 |
| RE3396M | RE3396 |
| RE3397M | RE3397 |
| RE3398M | RE3398 |
| RE3399M | RE3399 |
| RE3400M | RE3400 |
| RE3401M | RE3401 |
| RE3402M | RE3402 |
| RE3403M | RE3403 |
| RE3404M | RE3404 |
| RE3407C | RE3407 |
| RE3408C | RE3408 |
| RE3409C | RE3409 |
| RE3410C | RE3410 |
| RE3411C | RE3411 |
| RE3412C | RE3412 |
| RE3413C | RE3413 |
| RE3414C | RE3414 |
| RE3415C | RE3415 |
| RE3417C | RE3417 |
| RE3420C | RE3420 |
| RE3421M | RE3421 |
| RE3422C | RE3422 |
| RE3423C | RE3423 |
| RE3430C | RE3430 |
| RE3430M | RE3430 |
| RE3430X | RE3430 |

| | |
|---------|--------|
| RE3431C | RE3431 |
| RE3432C | RE3432 |
| RE3432M | RE3432 |
| RE3432X | RE3432 |
| RE3434C | RE3434 |
| RE3434R | RE3434 |
| RE3435C | RE3435 |
| RE3435R | RE3435 |
| RE3436C | RE3436 |
| RE3436R | RE3436 |
| RE3437C | RE3437 |
| RE3440C | RE3440 |
| RE3440R | RE3440 |
| RE3443M | RE3443 |
| RE3443X | RE3443 |
| RE3444C | RE3444 |
| RE3444M | RE3444 |
| RE3444X | RE3444 |
| RE3445M | RE3445 |
| RE3445X | RE3445 |
| RE3446C | RE3446 |
| RE3446M | RE3446 |
| RE3446R | RE3446 |
| RE3446X | RE3446 |
| RE3447M | RE3447 |
| RE3447X | RE3447 |
| RE3448C | RE3448 |
| RE3448M | RE3448 |
| RE3448X | RE3448 |
| RE3449C | RE3449 |
| RE3450C | RE3450 |
| RE3451C | RE3451 |
| RE3452C | RE3452 |
| RE3453C | RE3453 |
| RE3454C | RE3454 |
| RE3455C | RE3455 |
| RE3456C | RE3456 |
| RE3457C | RE3457 |
| RE3458C | RE3458 |
| RE3459C | RE3459 |
| RE3460C | RE3460 |
| RE3464C | RE3464 |
| RE3464R | RE3464 |
| RE3469C | RE3469 |
| RE3470C | RE3470 |
| RE3470M | RE3470 |
| RE3470X | RE3470 |
| RE3474C | RE3474 |
| RE3474R | RE3474 |
| RE3475C | RE3475 |
| RE3475N | RE3475 |
| RE3476C | RE3476 |
| RE3476M | RE3476 |
| RE3476X | RE3476 |
| RE3477C | RE3477 |
| RE3485C | RE3485 |
| RE3485N | RE3485 |
| RE3486C | RE3486 |
| RE3488C | RE3488 |
| RE3488N | RE3488 |
| RE3488R | RE3488 |
| RE3488X | RE3488 |
| RE3490C | RE3490 |
| RE3491C | RE3491 |

| | |
|---------|--------|
| RE3492C | RE3492 |
| RE3493C | RE3493 |
| RE3494C | RE3494 |
| RE3495C | RE3495 |
| RE3496C | RE3496 |
| RE3496N | RE3496 |
| RE3498N | RE3498 |
| RE3498R | RE3498 |
| RE3499C | RE3499 |
| RE3500C | RE3500 |
| RE3500R | RE3500 |
| RE3500X | RE3500 |
| RE3501C | RE3501 |
| RE3501R | RE3501 |
| RE3501X | RE3501 |
| RE3502C | RE3502 |
| RE3502X | RE3502 |
| RE3503C | RE3503 |
| RE3503N | RE3503 |
| RE3506C | RE3506 |
| RE3506R | RE3506 |
| RE3511C | RE3511 |
| RE3511M | RE3511 |
| RE3511R | RE3511 |
| RE3513C | RE3513 |
| RE3513N | RE3513 |
| RE3513R | RE3513 |
| RE3514C | RE3514 |
| RE3514R | RE3514 |
| RE3515C | RE3515 |
| RE3518C | RE3518 |
| RE3518R | RE3518 |
| RE3519C | RE3519 |
| RE3519R | RE3519 |
| RE3519X | RE3519 |
| RE3520C | RE3520 |
| RE3520M | RE3520 |
| RE3520N | RE3520 |
| RE3521C | RE3521 |
| RE3521M | RE3521 |
| RE3521R | RE3521 |
| RE3521X | RE3521 |
| RE3522C | RE3522 |
| RE3522R | RE3522 |
| RE3525C | RE3525 |
| RE3525M | RE3525 |
| RE3525N | RE3525 |
| RE3525R | RE3525 |
| RE3525X | RE3525 |
| RE3526C | RE3526 |
| RE3526M | RE3526 |
| RE3526X | RE3526 |
| RE3532C | RE3532 |
| RE3532M | RE3532 |
| RE3532R | RE3532 |
| RE3533C | RE3533 |
| RE3533M | RE3533 |
| RE3533R | RE3533 |
| RE3534C | RE3534 |
| RE3534M | RE3534 |
| RE3534R | RE3534 |
| RE3535R | RE3535 |
| RE3536C | RE3536 |
| RE3537C | RE3537 |

| | |
|---------|--------|
| RE3550X | RE3550 |
| RE3551X | RE3551 |
| RE3552X | RE3552 |
| RE3554C | RE3554 |
| RE3554M | RE3554 |
| RE3554R | RE3554 |
| RE3557C | RE3557 |
| RE3557M | RE3557 |
| RE3557R | RE3557 |
| RE3559M | RE3559 |
| RE3559X | RE3559 |
| RE3560C | RE3560 |
| RE3560M | RE3560 |
| RE3560X | RE3560 |
| RE3561M | RE3561 |
| RE3561X | RE3561 |
| RE3562C | RE3562 |
| RE3562M | RE3562 |
| RE3562R | RE3562 |
| RE3562X | RE3562 |
| RE3563M | RE3563 |
| RE3563X | RE3563 |
| RE3564C | RE3564 |
| RE3564M | RE3564 |
| RE3564X | RE3564 |
| RE3570C | RE3570 |
| RE3571C | RE3571 |
| RE3571R | RE3571 |
| RE3572X | RE3572 |
| RE3573X | RE3573 |
| RE3574X | RE3574 |
| RE3575X | RE3575 |
| RE3576X | RE3576 |
| RE3577X | RE3577 |
| RE3578X | RE3578 |
| RE3580X | RE3580 |
| RE3581X | RE3581 |
| RE3582X | RE3582 |
| RE3583X | RE3583 |
| RE3586X | RE3586 |
| RE3587C | RE3587 |
| RE3587N | RE3587 |
| RE3596C | RE3596 |
| RE3596M | RE3596 |
| RE3596X | RE3596 |
| RE3597C | RE3597 |
| RE3597M | RE3597 |
| RE3597X | RE3597 |
| RE3624X | RE3624 |
| RE3627C | RE3627 |
| RE3627X | RE3627 |
| RE3631C | RE3631 |
| RE3633C | RE3633 |
| RE3636C | RE3636 |
| RE3637C | RE3637 |
| RN0001C | RN0001 |
| RN0001R | RN0001 |
| RN0002N | RN0002 |
| RN0002R | RN0002 |
| RN0013C | RN0013 |
| RN0014R | RN0014 |
| RN0020C | RN0020 |
| RN0020R | RN0020 |
| RN0021C | RN0021 |

| | |
|-----------------|---|
| RN0021R | RN0021 |
| RN0021X | RN0021 |
| RN0022C | RN0022 |
| RN0022R | RN0022 |
| RN0022X | RN0022 |
| RN0023C | RN0023 |
| RN0023R | RN0023 |
| RN0023X | RN0023 |
| RN0027C | RN0027 |
| RN0027R | RN0027 |
| RN0028C | RN0028 |
| RN0028R | RN0028 |
| RN0028X | RN0028 |
| RN0029C | RN0029 |
| RN0029R | RN0029 |
| RN0030C | RN0030 |
| RN0030R | RN0030 |
| RN0031C | RN0031 |
| RN0031R | RN0031 |
| RN0031X | RN0031 |
| RN0032C | RN0032 |
| RN0032R | RN0032 |
| EX_HC00955(e) | L-3-Cyanoalanine exchange |
| EX_HC00001(e) | Albumin exchange |
| EX_HC00002(e) | Antichymotrypsin exchange |
| EX_HC00003(e) | Antitrypsin exchange |
| EX_HC00004(e) | ApoA1 exchange |
| EX_HC01787(e) | Lepidimoid exchange |
| EX_HC01852(e) | Fibrinogen exchange |
| EX_HC01939(e) | Haptoglobin exchange |
| EX_HC01942(e) | Plasminogen exchange |
| EX_HC01943(e) | Prothrombin exchange |
| EX_HC01944(e) | ApoTransferin exchange |
| EX_HC02192(e) | taurolithocholate exchange |
| EX_HC02193(e) | glycolithocholate exchange |
| EX_HC02195(e) | tauroursodeoxycholate exchange |
| EX_HC02196(e) | glycoursodeoxycholate exchange |
| EX_HC02220(e) | sulfochenodeoxycholate exchange |
| EX_HC02154(e) | GM4-pool exchange |
| EX_HC02175(e) | caprate exchange |
| EX_HC02199(e) | glutathionyl-leuc4 exchange |
| EX_HC02200(e) | S-glutathionyl-2-4-dinitrobenzene exchange |
| EX_HC02201(e) | S-glutathionyl-ethacrynic-acid exchange |
| EX_HC02172(e) | Zinc exchange |
| EX_HC02191(e) | lithocholate exchange |
| EX_HC02194(e) | ursodeoxycholate exchange |
| EX_HC02197(e) | sulfoglycolithocholate(2-) exchange |
| EX_HC02198(e) | 2-[(4R)-4-[(1S,2S,5R,7R,10R,11S,14R,15R)-2,15-dimethyl-5-(sulfonatooxy)tetracyclo[8.7.0 |
| EX_HC02187(e) | reverse-triiodothyronine exchange |
| EX_HC02180(e) | thromboxane-b2 exchange |
| EX_HC02179(e) | 20-hydroxy-arachidonate exchange |
| EX_HC02208(e) | prostaglandin-d1 exchange |
| EX_HC02210(e) | prostaglandin-d3 exchange |
| EX_HC02213(e) | prostaglandin-e3 exchange |
| EX_HC02214(e) | prostaglandin-flalpha exchange |
| EX_HC02216(e) | prostaglandin-f2beta exchange |
| EX_HC02217(e) | prostaglandin-g2 exchange |
| EX_CE1950(e) | cyanosulfurous acid anion exchange |
| EX_cynt(e) | Cyanate exchange |
| EX_cdpea(e) | CDP-ethanolamine(1-) exchange |
| EX_12dgr120(e) | 1,2-Diacyl-sn-glycerol (didodecanoyl, n-C12:0) exchange |
| FAOXC11BRC9BRx | fatty acid beta oxidation(C11br-->C9br)x |
| FAOXC13BRC11BRx | fatty acid beta oxidation(C13br-->C11br)x |
| FAOXC15BRC13BRx | fatty acid beta oxidation(C15br-->C13br)x |

```

FAOXC9BRC7BRm    fatty acid beta oxidation(C9br-->C7br)m
CARhPTtc          Transport of L-Carnosine by hPT3 or hPT4 peptide transporter.
CBLTDe           release of B12 by simple diffusion
BIDGLCURr        bilirubin di-glucuronide production
EX_adpcb1(e)      exchange reaction for Adenosylcobalamin
EX_oh1(e)         exchange reaction for hydroxide ion
FADtm            Transport of fad into mitochondria
NADtm            transport of NAD into mitochondria
-----end-----

```

Find mass leaks or siphons within the heuristically internal part, without using the bounds given by the model

```

if 1
    modelBoundsFlag=0;
    leakParams.epsilon=1e-4;
    leakParams.method='dc';
    leakParams.theta=0.5;

    [leakMetBool,leakRxnBool,siphonMetBool,siphonRxnBool,leakY,siphonY,statp,statn] =...
        findMassLeaksAndSiphons(model,model.SIntMetBool,model.SIntRxnBool,...
            modelBoundsFlag,leakParams,printLevel);
end

```

| | | |
|------|------|---|
| 2940 | 4559 | subset tested for leakage (dc method, with infinite flux bounds)... |
| 0 | 0 | semipositive leaking metabolites (and exclusive reactions). |
| 0 | 0 | seminegative siphon metabolites (and exclusive reactions). |

Find the maximal set of reactions that are stoichiometrically consistent

```

if ~isfield(model,'SConsistentMetBool') ||
~isfield(model,'SConsistentRxnBool')
    if strcmp(model.modelID,'HMRdatabase2_00')
        massBalanceCheck=0;
    else
        massBalanceCheck=1;
    end
    if 1

        [SConsistentMetBool,SConsistentRxnBool,SInConsistentMetBool,SInConsistentRxnBool,unknownSConsistencyMetBool,unknownSConsistencyRxnBool,model]...
            =findStoichConsistentSubset(model,massBalanceCheck,printLevel);

        else
            %print out problematic reactions to file
            resultsFileName=[resultsPath filesep model.modelID];

            [SConsistentMetBool,SConsistentRxnBool,SInConsistentMetBool,SInConsistentRxnBool,unknownSConsistencyMetBool,unknownSConsistencyRxnBool,model]...

            =findStoichConsistentSubset(model,massBalanceCheck,printLevel,resultsFileName);
        end
    end
end

```

```

end
end

```

```

-----
#mets      #rxns      totals.
2940      5190
-----
0          631      heuristically exchange.
2940      4559      heuristically non-exchange.
2203      4534      seemingly elementally balanced.
2203      4534      seemingly elementally balanced and stoichiometrically consistent.
737       656      seemingly elementally imbalanced.
-----
2203      4534      heuristically non-exchange and seemingly elementally balanced.
2203      4534      seemingly elementally balanced and stoichiometrically consistent.
737       25       heuristically non-exchange and seemingly elementally imbalanced.
-----
Iteration #1 minimum cardinality of conservation relaxation vector.
2940      4559      unknown consistency.
2940      4559      being tested.
2940      4559      ... of which are stoichiometrically consistent by min cardinality of stoich consistent
2940      4559      Confirmed stoichiometrically consistent by leak/siphon testing.
0          0        ... of which are of unknown consistency.
--- Summary of stoichiometric consistency ---
2940      5190      totals.
0          631      heuristically exchange.
2940      4559      heuristically non-exchange:
2940      4559      ... of which are stoichiometrically consistent.
0          0        ... of which are stoichiometrically inconsistent.
0          0        ... of which are of unknown consistency.
---
0          0        heuristically non-exchange and stoichiometrically inconsistent or unknown consistency
0          0        ... of which are elementally imbalanced (inclusively involved metabolite).
0          0        ... of which are elementally imbalanced (exclusively involved metabolite).
2940      4559      Confirmed stoichiometrically consistent by leak/siphon testing.
--- END ---

```

```

rxnBool=model.SInConsistentRxnBool & model.SIntRxnBool;
if any(rxnBool)
    if printLevel>0
        fprintf('%s\n','Stoichiometrically inconsistent heuristically non-
exchange reactions:')
    end
    for n=1:nRxn
        if rxnBool(n)

fprintf( '%20s\t%50s\t%s\n',model.rxns{n},model.rxnNames{n},model.subSystems{n}
})
        end
    end
    if printLevel>0
        fprintf('%s\n','-----')
    end
end

rxnBool=model.unknownSConsistencyRxnBool & model.SIntRxnBool;
if any(rxnBool)

```

```

    if printLevel>0
        fprintf('%s\n','Unknown consistency heuristically non-exchange
reactions:')
    end
    for n=1:nRxn
        if rxnBool(n)

fprintf('%20s\t%50s\t%s\n',model.rxns{n},model.rxnNames{n},model.subSystems{n
})

        end
    end
    if printLevel>0
        fprintf('%s\n','-----')
    end
end
end

```

Sanity check of stoichiometric and flux consistency of model with open external reactions

```

    if all(model.SIntMetBool & model.SConsistentMetBool)...
        && nnz(model.SIntRxnBool &
model.SConsistentRxnBool)==nnz(model.SIntRxnBool)...
        && all(model.fluxConsistentMetBool)...
        && all(model.fluxConsistentRxnBool)

[nMet,nRxn]=size(model.S);
    if printLevel>1
        fprintf('%6s\t%6s\n','#mets','#rxns')
        fprintf('%6u\t%6u\t%s\n',nMet,nRxn,' totals.')

fprintf('%6u\t%6u\t%s\n',nnz(~model.SIntMetBool),nnz(~model.SIntRxnBool),'
heuristically exchange.')
    end

    checksPassed=0;
    %Check that all heuristically non-exchange reactions are also
stoichiometrically consistent

    %exchange reactions
    model.EXRxnBool=strncmp('EX_', model.rxns, 3)==1;
    %demand reactions going out of model
    model.DMRxnBool=strncmp('DM_', model.rxns, 3)==1;
    %sink reactions going into or out of model
    model.SinkRxnBool=strncmp('sink_', model.rxns, 5)==1;
    %all heuristic non-exchanges, i.e., supposedly all external reactions
    bool=~(model.EXRxnBool | model.DMRxnBool | model.SinkRxnBool);
    if nnz(bool & model.SIntRxnBool &
model.SConsistentRxnBool)==nnz(model.SConsistentRxnBool)
        checksPassed=checksPassed+1;
        if printLevel>1

```

```

fprintf('%6u\t%6u\t%s\n',nnz(model.SIntMetBool),nnz(model.SIntRxnBool),' All
internally stoichiometrically consistent. (Check 1: minimum cardinality of
conservation relaxation vector.)');
    end
end

    %Check for mass leaks or siphons in the stoichiometrically
consistent part
    %There should be no leaks or siphons in the stiochiometrically
consistent part
    modelBoundsFlag=0;
    leakParams.epsilon=1e-4;
    leakParams.eta = getCobraSolverParams('LP', 'feasTol')*100;
    leakParams.method='dc';

[leakMetBool,leakRxnBool,siphonMetBool,siphonRxnBool,leakY,siphonY,statp,stat
n]...

=findMassLeaksAndSiphons(model,model.SConsistentMetBool,model.SConsistentRxnB
ool,modelBoundsFlag,leakParams,printLevel);

    if nnz(leakMetBool)==0 && nnz(leakRxnBool)==0 &&
nnz(siphonMetBool)==0 && nnz(siphonRxnBool)==0
        checksPassed=checksPassed+1;
        if printLevel>1
            fprintf('%6u\t%6u\t%s\n',nnz(leakMetBool |
siphonMetBool),nnz(leakRxnBool | siphonRxnBool),' No internal leaks or
siphons. (Check 2: leak/siphon tests.)');
        end
    end

    %Check that the maximal conservation vector is nonzero for each the
%internal stoichiometric matrix
    maxCardinalityConsParams.epsilon=1e-4;%1/epsilon is the largest mass
considered, needed for numerical stability
    maxCardinalityConsParams.method = 'quasiConcave';%seems to work the
best, but sometimes infeasible
    maxCardinalityConsParams.theta = 0.5;
    maxCardinalityConsParams.eta=getCobraSolverParams('LP',
'feasTol')*100;

[maxConservationMetBool,maxConservationRxnBool,solution]=maxCardinalityConser
vationVector(model.S(model.SConsistentMetBool,model.SConsistentRxnBool),
maxCardinalityConsParams);

    if nnz(maxConservationMetBool)==size(model.S,1) &&
nnz(maxConservationRxnBool)==nnz(model.SIntRxnBool)
        checksPassed=checksPassed+1;
        if printLevel>1

```

```

fprintf('%6u\t%6u\t%s\n',nnz(maxConservationMetBool),nnz(maxConservationRxnBo
ol),' All internally stoichiometrically consistent. (Check 3: maximim
cardinality conservation vector.)');
    end
end

    %Check that each of the reactions in the model (with open external
reactions) is flux consistent
    modelOpen=model;
    modelOpen.lb(~model.SIntRxnBool)=-1000;
    modelOpen.ub(~model.SIntRxnBool)= 1000;
    param.epsilon=1e-4;
    param.modeFlag=0;
    param.method='null_fastcc';

[fluxConsistentMetBool,fluxConsistentRxnBool,fluxInConsistentMetBool,fluxInCo
nsistentRxnBool,modelOpen] =
findFluxConsistentSubset(modelOpen,param,printLevel-2);

    if nnz(fluxConsistentMetBool)==size(model.S,1) &&
nnz(fluxConsistentRxnBool)==size(model.S,2)
        checksPassed=checksPassed+1;
        if printLevel>1

fprintf('%6u\t%6u\t%s\n',nnz(fluxConsistentMetBool),nnz(fluxConsistentRxnBool
),' All flux consistent. (Check 4: maximim cardinality constrained right
nullspace.)');
            end
        end

        if checksPassed==4
            %save the model with open exchanges as the default generic
            %model
            model=modelOpen;
            if printLevel>0
                fprintf('%s\n','Open external reactions is
stoichiometrically and flux consistent. A flux balance model generated from
a reconstruction. GREAT!!!!');
            end
        end
        save([resultsFileName '_consistent.mat'],'model')
    end
end

```

REFERENCES

Gevorgyan, A., Poolman, M. G., Fell D., Detection of stoichiometric inconsistencies in biomolecular models. Bioinformatics, 24(19):2245–51, 2008.

Fleming, R.M.T., et al., Cardinality optimisation in constraint-based modelling: Application to Recon 3D (submitted), 2017.

Brunk, E. et al. Recon 3D: A resource enabling a three-dimensional view of gene variation in human metabolism. (submitted) 2017.